

208 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

TABLE 2.—RESPIRATOR CLASSIFICATION

Respirator	General Design Features	Protection Provided
I. Air-Purifying Respirators.	Filter (chemical or mechanical, for removing contaminant or contaminants from inhaled air) and facepiece attached to filter directly or by means of short length of flexible rubber tubing. Entire device is carried by the wearer.	Against specific contaminants or types of contaminants. No protection against atmospheres deficient in oxygen.
A. Chemical-Filter Respirators.....	Canisters or cartridges containing suitable chemicals attached directly or by means of short length of rubber tubing to full face piece or half mask.	Against gaseous contaminants.
1. Gas Mask.....	Canisters with chemicals for individual gases or combinations thereof.	Up to 3% ammonia and 2% most other gases and/or vapors.
2. Chemical - Cartridge respirators	Cartridges with chemicals for individual gases or combinations thereof.	Against very low or nuisance concentration of gases and/or vapors.
B. Mechanical - Filter Respirators (commonly called dust respirators).....	Fibrous filter attached to half mask face piece directly or by means of a short length of flexible rubber tubing.	Against particulate contaminants.
1. Dust.....	Do.	Against dusts of all kinds.
2. Fume.....	Do.	Against fumes of various metals. Since fumes are probably more difficult to remove by mechanical filtration than other kinds of particulate matter with the possible exception of smokes, this respirator will protect against such particulate matter as dusts and mists.

ENGINEERING CONTROL OF AIR CONTAMINATION

209

TABLE 2—Continued

Respirator	General Design Features	Protection Provided
3. Mist.....	Fibrous filter attached to half mask face piece directly or by means of a short length of flexible rubber tubing.	Against mists as produced by spray-coating with paint and vitreous enamels, chromic acid mist as produced in chromium plating, and mists of other materials whose liquid vehicle does not produce harmful gases or vapors.
C. Chemical and Mechanical-Filter Respirator.....	Chemical and mechanical filter attached to face piece directly or by means of a short length of flexible rubber tubing.	Against combinations of gaseous and particulate contaminants.
II. Supplied-Air Respirators.		
A. Hose Mask with Blower.....	Blower (Manual or Power - operated), large diameter hose, harness, and face piece.	Against any atmosphere.
B. Hose Mask without Blower.....	Large diameter hose, harness, and face piece.	Against any atmosphere, but should not be used in immediately harmful atmosphere.
C. Air-Line Respirators..	Air supplied from special system or compressed air line to wearer through small diameter high pressure hose, reducing valve, short piece of flexible rubber tubing and face piece.	Do.
D. Abrasive Blasting....	Features same as 1, 2, 3 above (3 is more common) but in addition this device has suitable hood to protect wearer against rebounding abrasive.	Same as 1, 2, or 3 above, depending upon features but in addition has protection against impact and abrasion from rebounding abrasive material.

tion. They are used effectively, however, on jobs such as abrasive blasting, paint chipping, handling used storage battery plates,

210 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

cadmium oxide manufacture, welding operations, spraying of paints and glazes, the manufacture and use of pigments and dyes, and the like. Their most important use is under conditions where protection is required intermittently as in cleaning out operations; sweeping; after blasting; in removing cores from large foundry castings; shoveling, screening, and handling of materials; and the operation and maintenance of processing equipment.

It is the duty of management to decide whether respirators are needed. In no instance should they be selected as the control measure merely because they cost less than the other appropriate control systems. However, they may be used as a temporary expedient until the more satisfactory control measures have been placed in operation. If, after all the pertinent factors have been considered, it is concluded that respirators are needed, good respirators of the proper type should be purchased; they should be given to the workers with adequate instruction as regards the need for and proper wearing thereof, and a satisfactory system of maintenance should be set up.

The *selection* of the proper respirator is not an easy task. Some of the important factors which must be considered are: (1) nature of contaminant, that is, whether particulate or gaseous; (2) concentration of contaminant; (3) area of operation of wearer; (4) percentage of time respirator must be worn; (5) possible interference with operation, and (6) other protective devices needed by the wearer such as goggles, shields, or hoods. Table 2 will help in the selection of the appropriate device for a given operation.

Respirators, with the exception of the chemical cartridge type, are approved by the U. S. Bureau of Mines if they pass approval schedules formulated by that agency.¹³ A large variety of approved respirators is available today, and only respirators which bear this approval label should be used. Lists of approved respirators are available from the U. S. Bureau of Mines, Department of the Interior, Washington, D. C.

Maintenance, Housekeeping, and the Education of the Worker

Even though these three items are discussed individually in this section, they are interdependent. It is impossible to have good maintenance unless the housekeeping is good and the worker has been informed of the need for the control measures and the proper operation thereof. Any attempt to maintain working

equipment in good condition and to keep the work place in good order, is doomed to failure unless the worker is given the necessary instruction.

Maintenance.—It is not enough to purchase and install good, carefully designed equipment. Even the best equipment will become ineffective in a relatively short time unless it is maintained in good working condition. Maintenance is a duty of management and the worker. It is the duty of the worker to handle the equipment as intended, to keep it as clean as the nature of the operation will permit, to report to the management all signs of wear or failure and in very small industries to lubricate the moving parts. It is the duty of the management to provide the necessary personnel or instruct the proper personnel to inspect, lubricate, clean out, and repair the equipment routinely. Improper maintenance is evidenced by such indications as badly dented or collapsed hoods or ductwork; torn bags in bag-type collectors; ducts clogged with waste of all kinds, paper, or articles of clothing; collectors not functioning because they are not cleaned; dirty respirator filters; exhalation valves or filters missing from respirators; holes in ductwork; and ductwork badly corroded.

Much equipment such as the component parts of exhaust ventilation systems is expensive and an honest effort is usually made to maintain it in good condition to avoid the need for frequent replacements. However, respirators are relatively inexpensive and it is not unusual to find such equipment in use day in and day out without any provision for the maintenance thereof. Little good will be accomplished by the purchase of good respirators unless a satisfactory system is devised for their maintenance. These devices, even though rugged in construction, require daily inspection and cleaning if they are to function effectively.

The *most satisfactory method* of maintaining respirators in good condition is briefly as follows:¹⁴ (1) mark each worker's respirator with his employment number; (2) collect all used respirators at the end of each shift; (3) distribute the cleaned devices at the beginning of each shift; and (4) assign one employee, either part-time or full-time, if necessary, to the careful cleaning, sterilizing, and repairing of all respirators. The fact that each worker always gets his own respirator in a clean well-kept condition will go a long way toward overcoming the objections usually presented by workers against wearing such devices.

Housekeeping.—As used here, the term "housekeeping" refers principally to the general cleanliness and orderliness of the plant,

212 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

equipment, and machinery. Housekeeping is helped greatly by careful attention to details in the design of the plant so that the equipment and machinery are located in a methodical and systematic manner. In operating plants, housekeeping is a responsibility of the management and worker. It is the responsibility of the management to provide the requisites for good housekeeping, and it is the duty of the worker to use the facilities provided to the best advantage. Some of the *items* which are *essential* to good housekeeping are: (1) covers for containers; (2) vacuum cleaners, brooms, or hoses for cleaning; (3) shelves or compartments for storage of equipment or materials when not in use; (4) lockers for clothing; (5) toilets and wash rooms for personal hygiene; (6) trash and garbage receptacles—and they should be emptied frequently and cleaned routinely; (7) cuspidors, preferably of the disposable type, for workers who use chewing tobacco; and (8) barriers, guards, or baffles to prevent flying materials such as cutting oils, from getting on the floor and other equipment. Having a suitable place for everything and keeping everything in its proper place will go a long way toward keeping the general atmospheric contamination at a minimum.

Education of the Worker.—The education of the worker comprises two distinct subjects: (1) why something should be done, and (2) how it should be done. Such information is essential to the proper accomplishment of the workers' regular duties as well as to the proper operation and use of the various control devices. A worker cannot be expected to wear his respirator or goggles, or to turn on an exhaust blower, or open a damper unless he knows why he is doing it. Consequently, his education is of utmost importance and cannot as a rule be left entirely to the foreman. Frequent safety meetings and other meetings are necessary for the education of the worker in the proper use of his various safety and health equipment. Only by incessant instruction will the task of educating the worker be accomplished successfully.

SPECIFIC CONTROL MEASURES BY OPERATION

The present emergency has resulted in the introduction of many new operations and processes into industry and in the tremendous expansion of many operations and processes which were formerly done on a small scale. Consequently, new or increased health hazards are being constantly encountered.

While it is impossible to cover all of the new problems, there is presented herein in alphabetical order a number of new haz-

ards by operation and recommended control measures for the safe performance of these operations. In certain instances, it is desirable to refer to the chapter on *Occupational Dermatoses*.

Any material potentially toxic should be treated as though it were toxic until it has been shown to be otherwise.

All maximum allowable concentrations given in the following discussions are based on an average eight-hour daily exposure unless otherwise stated.

Abrasive Cleaning

Abrasive cleaning or abrasive blasting may be carried out with sand or steel shot as the abrasive. The health hazard associated with steel shot blasting operations is much less severe than with sand blasting operations; consequently steel shot should be used wherever possible. However, if steel shot is not available or results in an inferior product, sand should be used and can be used safely if the necessary precautions are observed, as given below:

Sandblasting.—The potential health hazard in sandblasting operations is dust of a high free silica content. The maximum allowable concentration of free silica (SiO_2) is five million particles per cubic foot of air (m.p.p.c.f.), as determined by the standard light field technique.

The dust hazard in sandblasting operations may be controlled by the following methods: (1) the use of properly designed mechanically exhaust-ventilated machines, cabinets, or rooms; (2) the use of personal protective devices; and (3) good house-keeping.

As a rule, *production abrasive cleaning operations* can be carried out in mechanical devices such as enclosed tumbling barrels, and rotary tables which are provided with adequate local exhaust ventilation. Wherever possible, devices of this nature should be used and should be maintained in good working condition so that their dust control effectiveness is not impaired. The amount of air which must be exhausted from the various types of automatic abrasive cleaning devices varies tremendously, depending upon a multitude of factors. In no instance, however, should the quantity of air exhausted be less than that required to produce a velocity of about 500 to 1000 f.p.m. at all openings from which dust might escape.

Abrasive cleaning which requires *manual operation* may be carried out in small mechanically exhaust-ventilated cabinets

214 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

which enclose the operation entirely with the exception of several holes in one wall to accommodate the hands and arms of the operator. Where possible, these access openings should be sealed with suitable flexible washers through which the hands may be inserted and which permit free movement of the arms for the operation. The precautions regarding maintenance and ventilation rate given in the previous paragraph apply for these devices also.

Large objects should be cleaned in suitable rooms or chambers which are provided with mechanical exhaust ventilation to prevent the dust from entering the surrounding atmosphere. These operations are usually conducted manually and the operator should be protected by means of a *supplied-air respirator* (*abrasive blasting helmet*) approved by the U. S. Bureau of Mines. The precautions concerning maintenance and the ventilation rate cited in the foregoing paragraphs should be observed for abrasive blasting rooms also.

It is usually economical to collect the abrasive sand from the dust collecting system for reuse. Whether or not this is done, the dust should be collected from the exhausted air before it is discharged to the outside and the discharge outlet should be located at a point which will prevent the reentrance of the contaminated air into the buildings. In no instance should the filtered air be recirculated into the building. The discharge of the dust collector hopper should be provided with a dust-tight flexible sleeve which is attached to the top, or extends to the bottom, of the receptacle for the collected material to prevent the escape of dust when the collector hopper is emptied.

Good housekeeping which includes such items as keeping the floor, ledges, and machinery free of sand and dust; emptying the collector hoppers frequently and routinely; maintaining all connections through which dust or dust-laden air are conveyed in a dust-tight condition; and cleaning, sterilizing, and repairing the personal protective devices daily will aid considerably in keeping the dust concentration in the inspired air at a safe level.

Shotblasting.—The potential health hazards in shotblasting operations are metallic dusts and silica dusts in those instances where objects having sand on their surfaces are cleaned. The maximum permissible safe concentration for some metallic dusts is fifty million particles per cubic foot of air; for free silica dust, five million particles, as determined by the standard light field

technique; and for lead dust, 0.15 milligrams per cubic meter of air (mg./m.³).

Even though the health hazard with shotblasting as a rule is much less severe than with sandblasting, the same general control measures are applicable. However, the various precautions need not be observed as rigidly as is the case with sandblasting.

Acid Pickling (see Pickling)

Acid (Nitric) Tank Filling

The potential health hazard associated with nitric acid tank filling is *oxides of nitrogen*. The currently accepted maximum allowable concentration of nitrogen oxides for an eight-hour daily exposure is 40 parts per million (p.p.m.).

In storage tanks where oxides of nitrogen are discharged while the tanks are being filled, the vents should be connected to an acid recovery plant or extended to a sufficient height to prevent injury to the workers through contact with the concentrated nitrogen oxides. Where necessary, the oxides of nitrogen should be removed from the exhausted air by means of a suitable wet collector.

Airplane Motor Cleaning

The operation of spraying airplane motors with gasoline to clean them after they have been tested presents a potentially serious exposure to gasoline vapor, and sometimes to lead. The maximum allowable concentration for gasoline vapor is 1000 p.p.m. and for lead is 0.15 mg./m.³. In addition, if leaded gasoline is used, the lead tetra-ethyl is absorbed readily through the skin.

Gasoline containing lead tetra-ethyl should never be used for this purpose. The spray cleaning operation should be carried out in a booth, cabinet, or small room provided with mechanical exhaust ventilation at the minimum rate of 150 c.f.m. per square foot of booth opening or room cross-sectional area. In addition, the worker should always remain upstream of the motor, that is, in the clean air.

Alkali Cleaning

The potential health hazards associated with cleaning parts in an alkali bath are high relative humidities and skin contact with the alkali.

216 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

Rooms in which alkali cleaning tanks are located should be provided with general mechanical ventilation with sufficient air removal to keep the relative humidity from attaining a value which would result in very uncomfortable working conditions.

The operator should wear protective clothing to prevent skin contact with the alkali.

Alumilting (Finishing Aluminum and Aluminum Alloy Products)

The health hazard in this operation is from exposure to the sulfuric acid gases and mists, liberated from the acid dipping tanks. While the maximum allowable concentration for sulfuric acid in the air has not been determined definitely, it is believed to be the same as for hydrochloric acid gas, namely, 10 p.p.m.

The hazard may be controlled by the use of slot-type lateral exhaust hoods along one or both long sides of the dipping tank and exhausting a minimum of 120 c.f.m. of air per square foot of tank area through the hoods.

Amatol Break-Up

The potential health hazard from breaking up solid amatol is the TNT in the amatol dust. The maximum allowable safe concentration for atmospheric TNT is 1.5 mg./m.³.

All amatol or TNT break-up operations should be carried out in an exhaust-ventilated booth with the worker upstream of the operation. The recommended minimum ventilation rate for such booths is 200 c.f.m. per square foot of booth opening.

If the operation is an intermittent one, and particularly if no adequately ventilated booth is available, the work may be done in an isolated location or on the outside so that the dust is not contributed to the air of a room occupied by other workers. The operator will receive adequate protection if he wears a U. S. Bureau of Mines approved mechanical filter respirator.

Amatol Bucket Cleaning (Steam Out)

The potential health hazard associated with amatol bucket cleaning is TNT vapors and fumes. The currently accepted maximum allowable atmospheric concentration for TNT fumes and vapors is 1.5 mg./m.³.

The water baths used to melt the TNT encrusted in the buckets should be enclosed as much as possible and provided with

a mechanical exhaust ventilation system adequate to give a minimum velocity of 100 f.p.m. across all face openings.

Amatol Cooling (Open Tubs) (see also TNT Cooling)

The potential health hazard associated with amatol cooling is TNT vapors and fumes. The currently accepted maximum allowable atmospheric concentration of TNT vapor and fumes for an eight-hour daily exposure is 1.5 mg./m.³.

This operation should be isolated in an area having good natural ventilation. Covers should be provided for the cooling kettles and all stirring should be done mechanically.

Amatol Pouring and Puddling

The principal potential health hazard associated with amatol pouring is TNT vapors and fumes. The currently accepted maximum allowable atmospheric concentration of TNT for an eight-hour daily exposure is 1.5 mg./m.³.

If this operation is carried out in well ventilated bays or rooms, no health hazard will exist under normal operating conditions. Good ventilation may be obtained by keeping all doors and windows open as much as possible and by supplying or removing an adequate quantity of air by mechanical means. The exact amount of air which must be handled depends upon several conditions and must be determined for each plant.

Frequently several dust-producing operations, such as riser break-out, amatol break-up, and tub cleaning, are conducted in the pouring bays. This contamination in addition to that contributed by the pouring and puddling operations produces a concentration in excess of the safe limit. Therefore such operations should not be done in the pouring bays. Also all workers in these bays should be rotated from job to job.

If the atmospheric TNT concentration is found to exceed the allowable limit, general ventilation should be improved; local exhaust ventilation should be provided at the major sources of air contamination; and for intermittent exposures, respirators approved by the U. S. Bureau of Mines for toxic dusts should be used.

Amatol Preparation

The potential health hazards associated with amatol preparation are TNT vapors and fumes and ammonium nitrate dust. The currently accepted maximum allowable atmospheric concentration of TNT vapor and fumes for an eight-hour daily exposure

218 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

is 1.5 mg./m.³. While ammonium nitrate dust is not considered highly toxic, all reasonable means should be used to keep the atmospheric concentration of this dust low in accordance with good engineering practice.

The mixing kettles should be enclosed and provided with local exhaust ventilation adequate to maintain a minimum face velocity of 100 f.p.m. when the doors of the kettles are open. Due precautions must be observed as regards the safety hazard associated with the collection of explosive dusts in the exhaust ventilation system. A chemical-cartridge respirator for organic vapors should be worn by the operator when he has his head in or near the kettle for cleaning operations.

Ammonia Oxidation (Nitric Acid Manufacture)

The potential health hazards in ammonia oxidation are ammonia and oxides of nitrogen. The maximum permissible safe concentration for ammonia is 100 p.p.m. for an eight-hour daily exposure; and for the oxides of nitrogen it is 40 p.p.m.

Leaks in and about the pump in the pump house are usually a source of constant atmospheric pollution with ammonia. Since the process is automatic and normally requires little attention, the exposure should not be serious if the workers are able to breathe without undue irritation for the short and infrequent periods of exposure. If the concentrations are sufficiently high to cause objectionable irritation, U. S. Bureau of Mines approved gas masks for ammonia should be worn as an emergency measure.

Ammoniacal gas should not be allowed to concentrate near the catalyst in the compressor house. If necessary, suitable local mechanical exhaust ventilation should be installed to keep the atmospheric ammonia concentration below 100 p.p.m.

The vent stacks from the compressors should be made sufficiently high to prevent the nitrogen oxides from contaminating the workroom atmosphere of the compressor house, surrounding buildings, and work area. If it is not practicable to prevent contamination by raising the stacks to a sufficient height, the effluent gases should be collected in a suitable wet collector.

Aniline Distillation

The potential health hazard associated with aniline distillation is aniline vapor. The currently accepted maximum allowable atmospheric concentration of aniline for an eight-hour daily exposure is 5 p.p.m.

Even though this is an enclosed process, in normal operating conditions, small amounts of aniline are liberated in the general room air. The atmospheric concentration of aniline may be kept below the toxic limit by means of roof ventilators equipped with mechanically driven fans and by keeping all doors and windows open as much as possible. The vents from the aniline water storage tanks should be extended outside the building to a point where the vapors will not reenter the building.

Since aniline is readily absorbed through the skin, direct skin contact should be avoided. Good personal and general cleanliness should be practiced by the workers.

Aniline Manufacture (Nitrobenzene Reduction)

The principal health hazards associated with the reduction of nitrobenzene are aniline vapor and nitrobenzene vapor. The currently accepted maximum allowable atmospheric concentration of each of the above substances for an eight-hour daily exposure is 5 p.p.m.

Since this is an enclosed process, only small amounts of these substances are liberated to the general room atmosphere under normal operating conditions. The atmospheric concentrations of these substances may be kept below their toxic limits by means of roof ventilators equipped with mechanically driven fans and by keeping the doors and windows open as much as possible.

These substances are readily absorbed through the skin. Therefore the necessary precautions should be taken to avoid skin contact with them. In addition, strict personal hygiene and general cleanliness should be enforced by the proper supervisory personnel.

Anodizing (see Electroplating)

Ballistics Testing

In ballistics testing the potential health hazards to the riflemen are oxides of nitrogen, carbon monoxide, lead, and silica dust, and to the observers at the butt ends of the range, lead and possibly silica dust.

The maximum allowable concentrations of these dusts and gases in the atmosphere for an eight-hour daily exposure are:

Oxides of nitrogen	40 p.p.m.
Carbon monoxide	100 p.p.m.
Silica (sand)	5 m.p.p.c.f.
Lead	0.15 mg./m. ³

220 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

To prevent atmospheric concentrations in excess of those given above, mechanical ventilation is necessary.

Penetration Ranges.—If the observer does not enter the range directly after test-firing ceases, the lead hazard at the target end of the range may be controlled by exhausting air at or near the target end at a minimum rate of 200 c.f.m. per square foot of cross-sectional area of the range. On the other hand, if the observer enters directly after the test-firing ceases, higher ventilation rates are necessary. Where conditions permit, this same ventilation will serve to control the rifleman's exposure if the air inlet is located at the firing end of the range. Otherwise, a separate exhaustor will be necessary for the firing room, in which case the air should be admitted at the center or toward the target end of the range. The supplied air should be heated, if necessary. Propeller-type fans will serve as exhaustors if the ductwork is kept at a minimum; otherwise, centrifugal fans will be needed.

Good housekeeping, particularly keeping the walls and floor of the ranges free of dust, will aid considerably in controlling the lead hazard. Daily sweeping or preferably washing with hose and water is suggested.

Velocity Ranges.—Same as *Penetration Ranges* except that lead hazard may be nil.

Function and Casualty, and Hangfire Ranges.—In these tests the rifleman may be exposed to lead and silica as well as to oxides of nitrogen and carbon monoxide. The interposition of a reasonably large room between the muzzle port and the sand butt, requiring the bullet to pass through a wall with a second port before entering the room containing the sand butt, will keep the agitated dust from being blown back to the rifleman. Both the intermediate room and the room containing the sand butt should be mechanically exhaust-ventilated at a rate sufficient to control the hazard. A minimum of 1000 c.f.m. per range is suggested, but greater quantities must be exhausted in some cases, particularly if several rifles are fired simultaneously into the same range.

If considerable sand is contained in the exhausted air, a collector should be included in the exhaust ventilation system to prevent a nuisance in the nearby areas and to reduce the abrasive action on the fan. The collector should be located upstream of the fan. The discharge stack should be so located that the contaminated air will not reenter occupied buildings.

Balloon Manufacture (see also Rubber Goods Fabrication)

The potential health hazards in the cementing operations in the manufacture of barrage balloons result from the exposure to the cement solvents. The solvents vary as indicated in the section under "Rubber Goods Fabrication" and the health hazards vary accordingly.

The health hazard may be controlled by (1) employing cements containing the less toxic solvents and (2) conducting as much as possible of the cementing on tables with local exhaust ventilation. About 75 per cent of the cementing operations can be performed on tables, leaving only 25 per cent to be done on the floor where adequate control is more difficult. The cementing tables should be provided with slot-type exhaust hoods along both long sides of the table top. The exhaust ventilation rate should be sufficient to maintain the workers' exposure below the maximum allowable concentration for these solvents being used. To accomplish this, an air removal rate of about 50 c.f.m. per square foot of table top is suggested. The exposure for the floor cementing operations may be controlled by providing good general ventilation (about 10 air changes per hour) and by exercising care to keep the cement and solvent containers closed as much as possible and to use only as much solvent as is necessary to soften the fabric surface.

The inspection and final seaming inside the balloon presents a health hazard which should be controlled by general ventilation (air change) in the balloon at the rate given by the following equation $Q = \frac{X}{m}$, which is explained in the earlier part of this chapter.

Barrage Balloon Manufacture (see Balloon Manufacture)**Benzene Nitration**

The potential health hazards associated with the nitration of benzene are nitrobenzene and benzene vapors. The maximum allowable concentrations, on the basis of an eight-hour daily exposure, are 5 p.p.m. for nitrobenzene and 100 p.p.m. for benzene.

Since the nitration of benzene is an enclosed process, there should be no appreciable amount of benzene and nitrobenzene vapors liberated into the general room air under proper operating conditions. The small amounts of vapor which may be

222 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

liberated normally may be kept below the toxic limit by means of roof ventilators with mechanically driven fans and by keeping the doors and windows open as much as possible.

If workers repairing benzene nitrators are exposed to nitrobenzene vapors, they should wear chemical-filter respirators (gas masks) or supplied-air respirators (type B hose masks) approved by the U. S. Bureau of Mines for protection against acid gases and organic vapors.

Boat (Rubber) Manufacture (see Rubber Goods Fabrication)

Booster Cavity Drilling

The potential health hazard in booster cavity drilling is TNT dust. The currently accepted maximum allowable concentration for TNT is 1.5 mg./m.³ of air for an eight-hour daily exposure.

This operation is usually not a very dusty one and can easily be made almost dust-free by the judicious use of local exhaust ventilation. A small hood will suffice, located near the operation or attached to the drill, through which sufficient air is exhausted to remove all the fine dust. The suggested ventilation rate is such that the velocity at the source of dust production is 200 f.p.m. Consideration should be given to the possible collection of the TNT dust in the exhaust line; to the collection of this dust from the exhausted air; and to the disposition of the collected TNT.

Booster Cup or Tube Loading

The potential health hazard in loading booster cups and tubes with tetryl pellets is tetryl dust. The concentration of tetryl dust in the atmosphere should be kept below 1.5 mg./m.³. (See *Tetryl Blending*.)

The alignment of the pellets for insertion into the tubes as well as the actual insertion of the pellets into the cups or tubes releases considerable dust to the atmosphere. This exposure may be controlled by means of appropriate exhaust ventilation.

For the usual operations, down draft ventilation through the loading and aligning trays or racks is recommended. The trays or racks need perforated or slotted bottoms and may be permanently connected with the exhaust system or may be temporarily placed on an appropriate frame on the work bench through which air is exhausted. The recommended minimum ventilation rate is 100 c.f.m. per square foot of tray or rack area or sufficient to produce a minimum removal velocity of 100 f.p.m. at

the source of dust production. A dust trap or hopper should be located below the tray or grille to catch large particles and the air borne dust should be removed by a suitable collector (preferably wet) before the air reaches the fan. The dust trap and collector should be cleaned frequently and routinely.

In lieu of the above method, the individual operations may be partially enclosed, with transparent material if necessary, and provided with exhaust ventilation. The enclosure should be open in the front to permit the worker to perform the necessary operations expeditiously. The exhaust ventilation rate should be not less than 100 c.f.m. per square foot of opening in the enclosure. Either down draft through a grille in the table top or lateral ventilation through a connection in the enclosure may be used.

Until the exposure is controlled by means of exhaust ventilation, the workers should wear U. S. Bureau of Mines approved mechanical filter respirators at all times while performing the aligning and loading operations. Clean cloth facelets should be provided on the respirator masks at least daily to prevent dermatitis where the mask touches the face.

Bullet Casting (see Lead Bullet Casting)

Camouflage Paint Manufacture

In the manufacture of some of the camouflage paints, a chlorinated phenol known as "Dowicide F" is used as a wood preservative and mildew preventive. The maximum allowable concentration for this material is not known, but it produces violent coughing and is very irritating to the throats of exposed personnel and consequently requires adequate control measures.

The operation of mixing the Dowicide F with other dry paint ingredients should be done in a completely enclosed area which is exhaust-ventilated at the rate of about five air changes per minute.

Carbide Tool Manufacture

In the manufacture of cemented carbide tools, the finishing operations (grinding to the desired shape and sawing tool tips) are very dusty. These high concentrations of fine dust seem to produce a lung involvement which is under thorough investigation at present. Pending the outcome of this investigation, the dust should be controlled at its source.

224 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

The dust may be controlled by means of local exhaust ventilation at rates suggested under *Grinding* for similar conditions. Collectors in the exhaust systems are advisable owing to the value of the material collected.

Cavity Drilling, Booster (see Booster Cavity Drilling)**Cold Tinning Process**

The health hazard associated with this operation is the exposure to high concentrations of atmospheric mercury and potentially to high concentrations of lead. The maximum allowable concentration for mercury is 0.10 mg./m.³ and for lead is 0.15 mg./m.³ based on an eight-hour daily exposure.

The cold tinning process may be used locally for finishing metal objects with a protective coat which will protect against rust even in the presence of steam. It is commonly used where hot tinning is impracticable and where paint will not endure. Briefly, the operation consists of (1) cleaning the metal surfaces with acid, (2) applying a bonding or adhesive coat of mercury amalgam (usually by manual rubbing with a compound containing mercury and compounds thereof), and (3) applying a protective coat of about half and half lead and tin by means of a metallizing gun.

The lead exposure is intermittent and usually of short duration and will be controlled adequately if the same precautions are taken as are necessary for applying the bonding coat. The compound containing mercury should be applied in a segregated or enclosed space which is provided with mechanical ventilation at the minimum rate of 20 air changes per hour or 150 c.f.m. per square foot of opening into the enclosing space, whichever is the higher, and the operator should wear a U. S. Bureau of Mines approved supplied-air (air-line) respirator at all times while performing this operation.

Colloiding (Nitrocellulose and Ether Mixing and Macerating in the Manufacture of Smokeless Powder) (Mix Houses)

The potential health hazards in the colloiding operations are alcohol and ether vapors.

Although the maximum permissible safe concentrations are controversial at present, an attempt should be made to keep these concentrations as low as is feasible and it is suggested that they should never exceed a total of 1000 p.p.m.

Adequate control of the vapors liberated in colloidizing operations may be accomplished by the judicious use of general and local exhaust ventilation. These ventilation systems should be tied in with the solvent recovery system, if economically feasible.

Owing to the nature of these operations, it is impossible to give specific recommendations for local exhaust ventilation. Slot-type hoods are suggested, attached to or located near the multiple funnel, which fits on the receptacles into which the mixers are dumped. The hoods should be exhaust-ventilated through a flexible metal hose which might be detachable from the hood if it is an integral part of or attached to the funnel device. The flexible metal tube might be connected to the solvent recovery system or to an auxiliary system, depending upon the various conditions. The ventilation rate should be such that the air movement toward the exhaust hood is at least 100 f.p.m. in the zone of vapor liberation.

In addition, good general ventilation will be necessary. Depending upon economic considerations, this should be accomplished by means of a mechanical ventilation system which may be part of the solvent recovery system; or it may be a separate system; or it may be partly separate and partly tied in to the solvent recovery system.

Each plant must be considered separately and the appropriate measures designed accordingly.

Before scraping the mixer blades, the mixers should be allowed to remain open sufficiently long to permit the vapors to escape. The workers should wear chemical-filter respirators (gas masks) or supplied-air (air-line) respirators approved by the U. S. Bureau of Mines for organic vapors.

The "air blowing" of mixers by compressed air which blows the ether alcohol vapors into the workroom atmosphere should be discontinued. The use of a suction-type exhaust hose attached to the mechanical exhaust ventilation system or to a suitable auxiliary system should be substituted.

Cotton Picking, Drying and Weighing

The potential health hazard in the picking, drying, and weighing of cotton is that of cotton dust. The maximum permissible safe concentration for cotton dust is the same as for other nuisance dusts, namely, 50 million particles per cubic foot of air. However in some instances, it is very annoying to the exposed workers in substantially lower concentrations.

226 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

Local mechanical exhaust ventilation should be employed at the picking end and at the weighing end of the cotton drying machine. The minimum rate of air movement at the source of the dust should be 100 f.p.m. Adequate collectors should be provided for this dust to prevent a nuisance around the building on the plant grounds.

If local exhaust ventilation fails to prevent a concentration of cotton dust which is a nuisance to the workers, they should wear mechanical-filter respirators approved by the U. S. Bureau of Mines.

Crack Testing, Mercury (see Mercury Crack Testing)

Cup Loading, Booster (see Booster Cup Loading)

Decarbonizing

The health hazard in decarbonizing operations results from exposure to the solvent vapors escaping from the decarbonizing tanks. The solutions used for decarbonizing vary considerably but usually contain kerosene, creosote oil, and ethylene dichloride. Whereas the specific toxicity of some of these solvents is unknown, it is known that most of them are definitely toxic and require control measures. (The maximum allowable concentration for ethylene dichloride is believed to be about 100 p.p.m.)

The control measures are the same as given under *Degreasing*, which immediately follows.

Degreasing

Potential health hazards in solvent degreasing operations are vapors of trichlorethylene, ethylene dichloride, carbon tetrachloride, or other highly volatile solvents. The maximum allowable concentrations for an eight-hour daily exposure to vapors of trichlorethylene, ethylene dichloride, and carbon tetrachloride are 200 p.p.m., 100 p.p.m. and 100 p.p.m., respectively.

Degreasing operations should be carried out in properly designed tanks which may or may not be provided with local exhaust ventilation but should have adequate cooling or condensing capacity. The atmospheric contamination with the solvent vapors is usually low enough to present no health hazard when (1) the tanks are small (not over 10 square feet in cross-sectional area), (2) the heat input and cooling capacity of the cooling coils are carefully regulated, (3) the tanks are located

in large rooms with high ceilings and not near open doors or windows, (4) the withdrawal rate of the cleaned objects is slow (not more than 12 f.p.m.), and (5) the general room ventilation is good. However, for large tanks, or for any tanks located near open doors or windows or in small rooms, local exhaust ventilation at the tanks is necessary. The usual type of ventilation consists of slot-type lateral exhaust hoods located along one or both long sides of the tanks at the upper edge. The recommended minimum exhaust ventilation rate may be computed as follows:

$$Q = 50 LW$$

where Q = the exhaust ventilation rate in c.f.m.,
 L = the length of the tank in feet, and,
 W = the width of the tank in feet.

The exhausted air should be discharged at a point outside the building where it cannot reenter occupied buildings.

Tight-fitting covers should be employed on degreasing tanks whenever possible.

The cleaning out of degreasers, particularly those in which the workers must enter the tanks in the process, may involve exposures to excessive concentrations of solvent vapors for limited periods of time. Such exposures may be prevented by airing out the machine after withdrawal of the liquid, and by the use of supplied-air respirators (air-line respirators or hose masks) approved by the U. S. Bureau of Mines, when the exposures are severe and when their use does not impede the workers too greatly. Chemical cartridge respirators do not afford adequate protection when the exposures are severe.

If the odor of solvent persists in the vicinity of the machine, or if the workers complain of ill effects, the concentration of solvent vapors in the atmosphere should be determined to ascertain the efficiency of existing controls. The atmospheric concentration of solvent vapors should not exceed the maximum allowable concentration for the particular solvent used.

When carbon tetrachloride has been used for degreasing and it is removed from the degreased object by a centrifugal process, the carbon tetrachloride vapors should be kept from the room atmosphere by suitable means, such as enclosing the centrifuge and exhaust ventilating the enclosure at the minimum rate of 100 c.f.m. per square foot of opening in the enclosure. The opening in the enclosure obviously should not be in the line of throw of the centrifuge.

228 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

The solvent containers which are used to hold carbon tetrachloride or other solvent used in small degreasing operations, such as wiping of metal parts, should be kept closed by tight-fitting covers whenever possible.

Dimethylaniline Sulfate (DMAS) Nitration (see Nitration)**Dimethylaniline (DMA) Sulfation**

The principal potential hazard in the sulfation of DMA is DMA vapor. Although no maximum allowable concentration has been established for exposure to DMA vapor, the toxicity of DMA is believed to be of the same order as that of aniline, the maximum allowable concentration of which is 5 p.p.m. It is suggested, therefore, that the atmospheric concentration of DMA be maintained below a value of 5 p.p.m. wherever practicable.

Exposure of DMA vapor should be eliminated or reduced as much as possible by enclosure of the sulfation process, and use of adequate local exhaust ventilation with discharge of all DMA vapor to the outside atmosphere. The discharge vents should be located in such a manner that reentrance of the vapors to the workroom is prevented.

Dinitrotoluene (DNT) Crushing and Screening

The potential health hazard in DNT crushing and screening operations is DNT dust. Although no maximum allowable concentration has been established for DNT in the atmosphere, the toxicity of DNT is believed to be of the same order as that of TNT; therefore, it is recommended that the concentration of DNT in the atmosphere be kept below 1.5 mg./m.³

Control of these operations should be secured by enclosing the operations, by the use of dust-tight sleeves, by the application of local exhaust ventilation, and by the use of personal respiratory protection where necessary. A program of strict personal hygiene should be observed at all times. Where possible, a gravity-type system should be used; the crushed DNT being discharged by gravity from the crusher onto the screen and, finally, the screened material falling into an enclosed receiving unit.

It is believed that complete enclosure of the operations will keep the atmospheric concentration of DNT below 1.5 mg./m.³ Local exhaust ventilation and respirators should be used only if the above method fails.

An enclosed, mechanically-operated crusher should be used. Care should be taken in filling the crusher to avoid dissemination of dust into the room atmosphere. Discharge of crushed DNT from the crusher onto the screen and from the screen into the enclosed receiving unit should be done through dust-tight sleeve connections which will prevent escape of dust into the workroom air. The receiving hopper, or other unit, located beneath the screen, should be enclosed completely and should be kept closed during the actual screening.

If the use of local mechanical exhaust ventilation is indicated by continued high concentrations of DNT in the atmosphere, consideration should be given to its application at the crusher, at the screen, and at the final receiving unit beneath the screen. The rate of air movement at the source of dust should be at least 100 f.p.m. and should be 200 or more f.p.m. at the very dusty operations. The contaminated air should be discharged to the outside atmosphere in a manner such that it cannot reenter the building.

If workers are exposed intermittently to concentrations of DNT dust in excess of 1.5 mg./m.^3 , they should wear mechanical-filter respirators approved by the U. S. Bureau of Mines.

Diphenylamine (DPA) Crystallization and Packing

The potential health hazards in the crystallization and packing of DPA are DPA vapors and dust. No maximum allowable concentration has been established for exposure to vapors and dust of DPA but the handling and processing of this material should be in accordance with good engineering practice.

Vapors of DPA should be removed from the crystallizers through canopy-type exhaust hoods which are located above the crystallizers and are exhausted mechanically to the outside atmosphere. The exhaust velocity in each case at the source of the vapor should be at least 100 f.p.m.

Dissemination of DPA dust into the room atmosphere should be controlled by installation of adequate side guards on the crystallizer discharge chutes, careful filling of the containers with crystalline DPA to prevent overflow, and maintenance of an effective clean-up schedule.

Electroplating

The potential health hazards associated with electroplating are chromic acid mists, metallic salts, cyanides, and other toxic

230 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

gases. The maximum allowable concentrations for some of the materials which are encountered are as follows:

Chromic acid mist	0.1 mg./m. ³
Arsenic (as arsine)	1 p.p.m.
Hydrogen cyanide	20 p.p.m.
Cadmium	0.1 mg./m. ³

If toxic gases and mists are liberated in the electroplating process, as is the case with chromium and arsenic electroplating, and some anodizing operations using dilute solutions of chromic acid and strong electric currents, local exhaust ventilation is necessary at the plating tank. A lateral exhaust slot-type ventilation system removing at least 120 c.f.m. of air per square foot of tank area is recommended. Where high current densities are used in anodizing or electroplating, much higher ventilation rates are needed to remove the air contaminant effectively. For proper functioning of the exhaust ventilation system, the level of the plating solution should be at least 4 inches below the exhaust slots.

If toxic gases and mists are produced in the plating of cadmium, copper, and zinc, the above recommended exhaust ventilation system should be used.

The electroplating of zinc, copper, and nickel from acid or neutral solutions (non-cyanide baths) does not give rise to toxic gases and mists and therefore does not require mechanical exhaust ventilation of the plating tank. However, good natural ventilation is recommended.

In those operations using a cyanide bath, care should be taken to avoid introduction of acid into the bath since hydrogen cyanide is liberated under these conditions. All cyanide baths should be conspicuously marked *poisonous*.

It is also essential that skin contact with the plating baths be prevented. Care should be exercised to prevent splashing of the plating bath.

For more detailed information on all phases of safety in electroplating, see reference 7.

For a discussion of the health hazards connected with the cleaning process prior to electroplating, see *Pickling*.

Fabric Coating (see also Rubber Goods Fabrication)

In addition to the materials mentioned under "Rubber Goods Fabrication" chlorinated paraffins, chlorinated phenols, antimony oxide, chromic oxide, and other similar materials are used in

weatherproofing, fireproofing, and mildewproofing of canvas fabrics such as tent cloth. These materials are largely dermatitis producers at room temperatures, but at elevated temperatures such as are employed in drying the fabric after it has been coated, vapors may be liberated from the chlorinated compounds.

The dermatitis may be prevented by means of suitable protective clothing and protective creams. The toxic vapors which may be liberated in the drying ovens should be removed by exhaust ventilating the ovens.

Forging

The potential health hazards associated with forging are carbon monoxide and high temperatures. The maximum allowable concentration of carbon monoxide for an eight-hour daily exposure is 100 p.p.m.

Good natural ventilation should be provided in order to avoid excessively high temperatures and this should be supplemented by mechanically-operated exhaust fans in roof ventilators.

Canopy-type hoods with large diameter stacks should be employed over the furnaces and if the atmospheric concentration of carbon monoxide exceeds 100 p.p.m., this ventilation should be improved by the use of propeller-type fans in the discharge stacks. The point of discharge should be so located that the exhausted air does not reenter any occupied buildings.

Propeller-type fans in these stacks will aid also in the maintenance of more suitable room temperatures.

Furnace (Coreless Induction) Lining Removal

The potential health hazard associated with the removal of the linings of coreless induction furnaces is silica dust. The maximum allowable concentration of free silica (SiO_2) for an eight-hour daily exposure is 5 m.p.p.c.f. of air as determined by the standard light field technique.

In removing the furnace lining, it is necessary for the worker to have his head and shoulders inside the furnace. Therefore, his exposure to dust is severe. Supplied-air (air-line) respirators approved by the U. S. Bureau of Mines should be worn for these operations, if possible.

If supplied-air respirators are impracticable, U. S. Bureau of Mines approved mechanical-filter respirators (for pneumoconiosis-producing dusts) should be worn. These respirators must be

232 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

cleaned and repaired daily if they are to give satisfactory service and protection.

Fuze Cavity Reaming (see Tetryl Reaming)

Glycerine Nitration

The potential health hazards associated with the nitration of glycerine are nitrogen oxides and nitroglycerine. The maximum allowable concentration of nitrogen oxides in the atmosphere is 40 p.p.m. Although the maximum allowable concentration for nitroglycerine is not known, it is relatively toxic and the atmospheric concentration should be kept as low as possible.

All glycerine nitrators should be completely enclosed and located in rooms having good general ventilation.

In addition to absorption by inhalation, nitroglycerine is absorbed readily through the skin. Therefore, special attention should be paid to housekeeping (cleanliness of workroom) and to personal hygiene which should include changing work clothes daily, washing hands and face thoroughly before eating, taking showers at end of shift, and wearing protective clothing such as impervious gauntlets and gloves.

Grinding

The potential health hazards associated with grinding operations are abrasive, metallic, and lead dusts. The maximum permissible safe concentrations of the abrasive and metallic dusts will vary with the chemical composition of the dust generated but should never exceed 50 m.p.c.f. of air as determined by the standard light field technique. The maximum allowable concentration of lead in the atmosphere is 0.15 mg./m.³

Control in grinding operations should be accomplished by the use of wet grinding, general exhaust ventilation, local exhaust ventilation, or personal respiratory protective devices.

Wet grinding operations do not require local exhaust ventilation. Good general room ventilation may be necessary if the operations are of such magnitude as to produce excessive mist and humidity.

Continuous dry grinding operations should be provided with local mechanical exhaust ventilation. The exhaust hoods should be so located that the dust thrown off from the grinding wheels will be in the direction of the air flow into the hood. The following exhaust duct sizes and rates of air removal are recommended:

STANDARD GRINDER HOOD

Wheel Diameter (Inches)		Wheel Width (Inches)	Diameter of Exhaust Outlet (Inches)	Volume of Air Removed through Hood at 4500 f.p.m. Duct Velocity (c.f.m.)
Minimum	Maximum			
—	9	1.5	3	221
Over 9 . . .	16	2	4	392
Over 16 . . .	19	3	4.5	497
Over 19 . . .	24	4	5	614
Over 24 . . .	30	5	6	884

For more detailed information see references 15 and 16.

Where portable grinders are used, particularly if lead coated materials or materials containing considerable lead, such as solder, are being ground, U. S. Bureau of Mines approved respirators for toxic dusts should be worn if control by means of ventilation is either inadequate or impracticable.

Heat Treating

The principal potential health hazard in heat treating operations is carbon monoxide. The maximum allowable concentration for carbon monoxide in the atmosphere is 100 p.p.m. Other potential health hazards are cyanide and acrolein in certain types of heat treating. The currently accepted maximum allowable concentration for hydrocyanic acid gas is 20 p.p.m. and for acrolein, 1 p.p.m.

Heat treating furnaces should be examined periodically for defective equipment which would permit the escape of carbon monoxide into the workroom atmosphere. Partial control of carbon monoxide may be obtained by the use of suitable hoods enclosing the furnaces as much as possible and allowing the carbon monoxide and excessive heat to be removed by convection currents. If the above control is inadequate, as shown by the presence of excessive concentrations of carbon monoxide, the exhaust ducts from the hoods should be equipped with fans to provide mechanical exhaust ventilation and thereby increase the rate of air removal sufficiently to maintain the atmospheric concentration of carbon monoxide within the maximum allowable limit.

The excessive room temperatures which are commonly met in heat treating workrooms should be reduced by the use of natural ventilation where possible and by the use of roof ventilators equipped with mechanically operated exhaust fans.

234 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

Cyanide heat treating units should be controlled by the use of measures similar to those listed above.

The use of oil quenching baths in connection with heat treating operations presents possible hazards from acrolein, if vegetable oil is present in the quenching oil, and from carbon monoxide. The possibility of exposure to carbon monoxide is reduced by avoiding operation of oil quenching baths at excessively high temperatures, that is, by controlling the temperature of the substance to be quenched. The use of mineral oil as a quenching material eliminates the possibility of exposure to acrolein.

Igniter Mixture Preparation

The potential health hazard in the preparation of igniter mix is dust composed of igniter mix components. Even though the specific toxicity of these dusts is not known, it is believed that the total amount of dust in the atmosphere should not exceed 5.0 mg./m.³ and for barium peroxide the value should not exceed 0.5 mg./m.³

The exposure time at these operations is short and intermittent and adequate protection may be obtained through the use of mechanical-filter respirators approved by the U. S. Bureau of Mines.

Incendiary Mixture Preparation

The potential health hazard in the preparation of incendiary mixture is carbon tetrachloride. The maximum allowable concentration of carbon tetrachloride is 100 p.p.m. for an eight-hour daily exposure.

All contaminated air from the blender discharge and the granulation of the blended material should be removed by adequate local exhaust systems and discharged to the outside atmosphere. No recirculation of air contaminated with carbon tetrachloride should be permitted.

Lead Bullet Casting

The potential health hazard associated with the operation of casting lead bullets is atmospheric lead. The maximum allowable concentration of lead in the air is 0.15 mg./m.³ based on an eight-hour daily exposure.

Partial enclosure of the operations and exhaust ventilation of the enclosure or local exhaust hoods near the source of contamination serve to control this exposure adequately. The ventila-

tion rate should be such that the air velocity into the openings of the enclosure is not less than 100 f.p.m. and for local exhaust hoods it should be adequate to produce an air velocity in the proper direction at the source of contamination of at least 100 f.p.m.

Lead Burning

The principal potential health hazard in lead burning operations is lead fumes. The maximum allowable concentration for an eight-hour daily exposure to lead in the atmosphere is 0.15 mg./m.³ of air.

When lead burning is performed as a continuous operation at a fixed location, as on a workbench, a system of downdraft ventilation should be installed, consisting of a grille top workbench through which air is removed at a minimum rate of 200 c.f.m. per square foot of grille area.

When lead burning is performed as a continuous operation, but where some variation of the site is necessary, local exhaust ventilation should be provided by means of an adjustable, flexible tube with a mechanical source of exhaust ventilation. This tube should be three or four inches in diameter; the inlet should be located as close to the operation as practicable, and the source of exhaust should be sufficient to remove a minimum of 250 c.f.m. of air from each operating site.

When lead burning is a temporary or occasional operation, the workers should be required to use respirators approved by the U. S. Bureau of Mines for protection against lead fumes (type C supplied-air, if possible, otherwise mechanical-filter).

Lead Melting

The potential health hazards in lead melting operations are lead fumes and lead dust. The maximum allowable concentration for an eight-hour daily exposure to lead in the atmosphere is 0.15 mg./m.³ of air.

The melting pot or furnace should be enclosed with a hood and this hood should be connected to a source of mechanical exhaust ventilation capable of producing an air removal velocity of 100 f.p.m. at the hood openings. The fumes should be discharged to the outside atmosphere. The hood door should be closed except when it is necessary to remove melted lead from the furnace prior to pouring operations.

The *principal source of lead* is in the removal of lead dross

236 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

from the melting pot or furnace, and the deposition of this dross in a haphazard fashion upon the floor in the vicinity of the melting furnace or the molds. The lead dross should be removed carefully and deposited in a suitable receptacle which should be closed whenever possible by means of a tight-fitting cover.

Lead Pouring

The potential health hazards in lead pouring operations are lead fumes and lead dust. The maximum allowable concentration for an eight-hour daily exposure to lead in the atmosphere is 0.15 mg./m.³ of air.

The temperature of the molten lead should be kept as low as possible while still permitting the pouring operation. Good house-keeping should be maintained in the vicinity of the pouring operation, and periodic checks should be made for the presence of lead fumes and lead dust in the atmosphere.

The disposal of lead dross should be controlled as outlined under *Lead Melting* to minimize the exposure of the workers to lead dust. Care should be taken to deposit the dross within the receptacle provided, so that lead dust will be controlled effectively.

Leather Cleaning

The potential health hazards in leather cleaning operations are solvent vapors. Some of the more commonly used solvents are Varsol, carbon tetrachloride, ethylene dichloride, sulfur dioxide as an acid sulfite, and mineral cleaning oils; the established maximum allowable concentrations for some of these materials are listed in the table at the end of this chapter. Solvents of low toxicity should be used in all cases in leather cleaning.

If the concentration of a particular solvent vapor in the atmosphere exceeds the maximum allowable concentration, adequate general ventilation or a local exhaust ventilation system should be provided. If local exhaust ventilation is used, the air velocity at the source of the solvent vapor should be about 100 f.p.m.

Lens Cleaning

The potential health hazards in lens cleaning operations are solvent vapors. Some of the more commonly used solvents are xylene, coal-oil, higher alcohols, and the soapless cleaning compounds; the established maximum allowable concentrations for some of these materials are listed in the table at the end of this

chapter. Solvents of low toxicity should be used in all cases in lens cleaning.

If the concentration of a particular solvent vapor in the atmosphere exceeds the maximum allowable concentration, adequate general ventilation or a local exhaust ventilation system should be provided. If local exhaust ventilation is used, the air velocity at the source of the solvent vapor should be about 100 f.p.m.

Luminous Dial Painting

The potential health hazards in luminous dial painting and in the storage and handling of radioactive luminous compound incidental to dial painting are radioactive dust, gamma-rays, and radon, a gaseous decomposition product which is potentially dangerous when inhaled in excessive quantities. In addition to the commonly recognized luminous compounds, zinc sulfide, which has been given fluorescent properties by exposure to radium, should be handled with caution.

The exposure to gamma-rays should never exceed the rate of 0.1 roentgen per eight-hour working day per person. The maximum allowable concentration of radon gas in the atmosphere at any time is 10^{-11} curie per liter. See reference 17.

If the exposure to gamma-rays exceeds 0.1 roentgen per eight-hour working day per person, lead screening should be utilized to limit the exposure. The screening should conform to Failla's radium protection chart. See reference 18.

Control of radioactive dust and radon should be accomplished by (1) limiting the amounts of radioactive luminous compound issued to the workers, (2) partial or complete enclosure of processes, (3) the use of mechanical local exhaust ventilation, (4) general ventilation, (5) application of strict personal hygiene measures, and (6) personal respiratory protection.

Not more than the following amounts of radioactive luminous compound should be issued to each dial painter:

<i>Luminosity</i> (Microlamberts)	<i>Permissible Amount</i> (Grams)
0-12	20
12-38	10
38 or over	5

Where wet processing is impracticable in removing radioactive luminous compound preliminary to the repair or refinish-

238 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

ing, the article should be placed on a moist paper during the removal operation and the worker should wear a supplied-air (air-line) respirator approved by the U. S. Bureau of Mines for protection against toxic dusts. Such respirators should be worn by all persons exposed to dust from radioactive luminous compound, including weighing and compounding activities.

The *main sources of radon* in radium dial painting, handling and storage operations are: (1) the painting process itself and specifically from the paint stored in the container and being applied to the work, (2) the finished dials not yet removed to the drying cabinet, (3) the dials as they rest in the drying cabinet, (4) the storage cabinet preparatory to shipment, and (5) the storage cabinet at the point of use. Controls must be applied at these points.

Each dial painting bench should be equipped with a transparent hood which encloses the bench with the exception of an open working face, and which is exhausted mechanically at a minimum average rate of 50 f.p.m. (100 f.p.m. preferred) at the hood face. See U. S. Bureau of Standards Handbook H27 for hood specifications.

Cabinets in which painted dials are stored or dried should be ventilated at either of the following rates: (1) not less than 360 c.f.m. per 1,000 dials stored, (2 to 10 pointers equivalent to one dial), and (2) not less than that sufficient to produce an average face velocity of 75 f.p.m. across the cabinet doorway when the door is open.

In addition, general ventilation should be provided in all rooms in which radioactive luminous compound is used or handled so that the radon content of the air in the room should not exceed 10^{-11} curie per liter.

Every employee should be instructed in the handling of radioactive luminous compound and in the observance of all rules that immediately affect or concern his conduct. Proper supervision of all workers should be maintained to insure the observance of these rules.

All dial painters and others handling radioactive luminous compound should change clothing before and after each day, observe strict personal hygiene, and be inspected by supervising personnel under ultraviolet light for traces of radioactive luminous compound whenever they leave the workroom. If any of the compound is detected on the skin or clothing, it should be removed promptly.

ENGINEERING CONTROL OF AIR CONTAMINATION 239

For detailed information concerning the workrooms and equipment, inspection for hazards, transportation, and plant and personal hygiene, reference should be made to the U. S. Bureau of Standards Handbook H27, cited above.

Machining

Machining operations frequently involve the use of white lead and cutting oils. The potential health hazard is lead which may be ingested or absorbed through the skin directly or through the medium of the cutting oil.

A nontoxic lubricant should be used if possible in place of the white lead and all workers exposed to this hazard should observe strict personal hygiene, with particular attention to cleansing of hands before meals.

Magnesium Casting

This is a relatively new industry and presents some new potential hazards to health. The substances which are of concern as regards the health hazard are hydrogen fluoride, fluoride salts, and sulfur dioxide. The maximum allowable concentration for hydrogen fluoride is 3 p.p.m., and for sulfur dioxide is 10 p.p.m. based on an eight-hour daily exposure.

Whereas fluorides apparently are used in some magnesium casting, it has been found that their use is not essential, at least in some of the casting operations. Sulfur is used in the casting operation and sulfur dioxide is liberated during pouring; also, subsequent curing operations result in sulfur dioxide exposure. As a rule, the exposures are not serious and only under unusual conditions is a hazardous concentration encountered and then only for short periods. U. S. Bureau of Mines approved chemical-filter respirators (gas masks) for acid gases should be available for use when high concentrations are encountered.

Magnesium Screening (see Tracer Mix Preparation)**Mercury Crack Testing**

The potential health hazard in mercury crack testing is mercury vapor. The maximum allowable concentration of mercury vapor for an eight-hour daily exposure is 0.1 mg./m.³

The work table upon which the cartridges are coated with mercury, the sink into which the mercurous nitrate is poured, and the stove used for heating the coated cartridges and cases should be provided with adequate ventilation by means of a

240 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

laboratory bench-type hood under which the operations are performed. This hood should be exhaust-ventilated at a minimum rate of 150 c.f.m. per square foot of face opening in the hood.

The use of pitchers rather than shallow glass dishes for the mercury coating process will tend to keep the mercury concentration lower since less surface is exposed in this manner. All mercury coated cases and cartridges should be discarded into a covered container and these containers should be removed frequently from the laboratory (at least twice per shift is necessary).

Rubber gloves and rubber aprons should be worn by the examiners during the visual inspection of the mercury coated cases and cartridges.

Where adequate control measures are not available or have broken down, U. S. Bureau of Mines approved chemical-filter respirators (gas masks) or supplied-air (air-line) respirators for mercury vapor should be worn as an emergency measure until the proper control measures are in operation.

Metal Cleaning (see Pickling)**Metal Finishing (Caustic Treatment to Produce a Gun-Metal Finish)**

The health hazard in this operation results from exposure to the caustic mists and vapors liberated from the hot caustic solution into which the metal is dipped for treatment. The composition of the caustic solutions varies considerably and little is known concerning the maximum allowable concentrations; however, control measures are needed.

The caustic mists and vapors may be prevented from entering the general workroom air by the use of local exhaust ventilation at the hot caustic tanks. The recommended procedure consists of exhausting air at a minimum rate of 120 c.f.m. per square foot of tank area through slot-type lateral exhaust hoods located on one or both of the long sides of the tank.

Metal Spraying (Metalizing)

Metal spraying operations subject the operators to potential health hazards from metal fumes of all kinds including lead. The maximum allowable concentration of these metal fumes varies from as little as 0.15 mg./m.³ for lead to as much as 15 mg./m.³ for zinc and even more for iron.

Such operations should be performed in properly designed

booths which are exhaust-ventilated at the minimum rate of 200 c.f.m. per square foot of opening at the face of the booths, and the workers should always be on the clean air side of the object being sprayed.

Motor Testing

The potential health hazards in the testing of motors (tank, automobile, aviation engines, and so forth) are carbon monoxide and excessive noise. The maximum allowable concentration of carbon monoxide for an eight-hour daily exposure is 100 p.p.m. Testing motors in a fixed position requires the discharge of the exhaust gases to the outside air if workers are in the same room as the motor. If back pressure on the motor is of no consequence, the motor exhaust pipes may be extended to the outside. Where back pressure is not permissible, the motor exhaust pipes should enter a mechanically exhaust-ventilated duct from which air is removed in excess of the maximum rate of exhaust from the motor. In either case, the discharge should be located at a point where the contaminated air will not enter any occupied buildings.

When motors are tested on a moving assembly line, down-draft exhaust ventilation should be provided through grilles in the floor beneath the assembly line. Sufficient air should be removed to keep the *carbon monoxide concentration* in the general room air less than 100 p.p.m.

For automobile engine repair and test work, flexible metal ducts of suitable diameter to fit over the motor exhaust pipe should be used to convey the exhaust gas from the exhaust pipe to (1) a mechanically exhaust-ventilated gutter in the floor, (2) a mechanically exhausted duct, or (3) directly to the outside. If method (3) is used, the motor under test should be located as close as possible to the door or wall so that the length of flexible pipe is kept at a minimum. Good general room ventilation in addition is advisable.

Excessive *noise* should be controlled, if possible, by means of suitable sound baffles, sound absorbing materials, and enclosure of the source of noise. Where adequate control cannot be obtained by these methods, the exposed workers should wear suitable ear protective devices.

Nitration, Dimethylaniline Sulfate

The potential health hazards associated with DMAS nitration are nitrogen oxides. The maximum allowable concentration of

242 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

oxides of nitrogen for an eight-hour daily exposure is 40 p.p.m.

Since DMAS nitrators are enclosed and held under a slight negative pressure to remove the oxides of nitrogen liberated during the nitration reaction, there is little chance for oxides of nitrogen to be discharged to the general room air during normal operation. As an additional safety measure, the nitrators should have an auxiliary exhaust ventilation system to remove the nitrogen oxides in case of a breakdown or overloading of the exhaust system used to carry the nitrogen oxides to the acid recovery plant.

Nitrobenzene Distillation

The potential health hazard associated with nitrobenzene distillation is nitrobenzene vapor. The currently accepted maximum allowable safe concentration of nitrobenzene is 5 p.p.m.

The process should be completely enclosed and mechanical general room ventilation should be provided. Adequate ventilation may be provided by using roof ventilators equipped with mechanically operated fans. All doors and windows should be kept open as much as possible.

The overflow vents of the nitrobenzene storage tanks should extend outside the building to a point where the vapors will not reenter the building.

Nitrobenzene Neutralization, Separation and Storage

The potential health hazard associated with the neutralization, separation and storage of nitrobenzene is nitrobenzene vapor. The currently accepted maximum allowable concentration is 5 p.p.m.

The neutralization, separation and storage tanks should be completely enclosed. The overflow vents of the storage tanks should extend outside the building, at a point where the vapors will not reenter. Roof ventilators with mechanically operated fans should be provided for good general room ventilation.

Workers should observe strict precautions regarding general and personal cleanliness. Skin contact with nitrobenzene should be avoided.

Nitrocellulose Cutting and Graining

The potential health hazard found in cutting and graining of smokeless powder is from the ether and alcohol vapors.

Although the permissible safe concentrations are controver-

sial at present, an attempt should be made to keep the concentrations as low as is feasible and it is believed that they should never exceed a total of 1000 p.p.m.

In rifle powder graining the containers under the distributors should have a bottom made of wire screening or perforated metal and should be located on a grille over a well in the floor which is exhaust-ventilated. The ventilation rate should be as low as is consistent with adequate control; a minimum of 100 c.f.m. per square foot of grille area is suggested.

In powder cutting the containers of grained powder should be placed over a well in the floor similar to that advocated for powder graining. The local exhaust ventilation should be connected to the solvent recovery system. The buckets used to collect the cut powder should be constructed similar to those used for graining. By placing these over wells which are exhaust-ventilated, the vapors are prevented from escaping into the atmosphere.

In cold weather the supplied air should be introduced into the room at a low velocity to prevent a dangerous draft over the workers.

Nitroglycerine Neutralization and Washing

The potential health hazard associated with the washing and neutralization of nitroglycerine is inhalation of nitroglycerine vapor and skin contact with nitroglycerine. While the maximum allowable safe concentration for nitroglycerine has not been established, its toxicity is relatively high and therefore the atmospheric concentration should be kept as low as possible; all nitroglycerine neutralizing and washing operations should be enclosed as completely as possible, and good general room ventilation should be provided.

In addition to being absorbed by inhalation, nitroglycerine is absorbed readily through the skin. Therefore, special attention should be paid to housekeeping (cleanliness of workroom), and to personal hygiene, which should include changing work clothes daily, washing hands and face thoroughly before eating, taking shower at end of shift, and wearing protective clothing such as impervious gauntlets and gloves.

Nitrometer Operation

The principal health hazards associated with the nitrometer operation are mercury vapors and oxides of nitrogen. The maxi-

244 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

imum allowable atmospheric concentration of mercury vapor for an eight-hour daily exposure is 0.1 mg./m.³ while that of the oxides of nitrogen is 40 p.p.m.

Good housekeeping is essential in the prevention of mercurial poisoning. A collecting pan of sufficient size to receive any mercury spilled at the nitrometer should be installed just under the base supporting the nitrometer. The pan should slope to a central point and connect to a well to catch the spilled mercury. This well should be emptied frequently. The mercury should not be allowed to come in contact with any heated surface.

The nitrogen oxides from the nitrometer should not be permitted to enter the room air. These gases should be removed either by providing lateral mechanical exhaust ventilation at the point of discharge of the nitrogen oxides or by locating the nitrometer near a laboratory exhaust hood and attaching one end of a glass or rubber tube to the gas discharge end of the nitrometer and extending the other end of the tube well up into the laboratory exhaust hood or duct.

Paint Drying

The potential health hazard associated with drying painted articles is the vapor of the paint solvent. The toxicity of these solvents varies from the very toxic benzene to the relatively non-toxic acetone. The maximum allowable safe concentrations in the atmosphere for some of these solvents are listed in the table at the end of this chapter.

Drying of painted articles should be carried out in enclosed drying ovens provided with mechanical exhaust ventilation. The air removal rate should be sufficient to provide a minimum air velocity of 100 f.p.m. across the face of all openings in the drying oven. The point of discharge of the exhausted air should be so located that the vapors cannot reenter any occupied building.

Painting, Brush

The potential health hazards associated with brush painting are the paint pigments and the vapor of the paint solvent. Some of the more toxic pigment ingredients are lead and antimony, whereas the relatively harmless ingredients include zinc and iron. The toxicity of the solvents varies from the highly toxic benzene to the relatively non-toxic acetone. The maximum permissible safe concentrations for some of the solvents and pigment ingredients are listed in the table at the end of this chapter.

The important methods for controlling the health hazards of brush painting are: (1) the use of paints having relatively harmless solvents and pigments, (2) the use of adequate ventilation, (3) the use of suitable personal protective devices, and (4) good personal hygiene.

For the purpose of this discussion, only brush painting pertaining to the repair or construction of buildings and equipment will be considered. Where brush painting is part of a production job, the control measures listed under spray painting (*Painting, Spray*) should be applied.

Even though good ventilation is needed for brush painting of all kinds, special attention should be paid to the ventilation when paints containing the more toxic ingredients are used. Good natural ventilation provided by open doors and windows will suffice in large airy rooms, whereas some mechanical means such as a fan or blower will be needed to provide ventilation in smaller rooms where painting is being done.

For painting in small enclosed spaces, a supplied-air respirator approved by the U. S. Bureau of Mines should be used if definite mechanical ventilation is impracticable.

Good personal hygiene is very important in all manual painting. The hands and face should be kept clean by frequent and thorough washing, clothes should be changed frequently, dirty hands and soiled objects should be kept out of the mouth, and other items of personal cleanliness should be practiced.

Painting, Spray

The potential health hazards associated with spray painting are the paint pigments and the mist and vapor of the paint solvent. Some of the more toxic pigment ingredients are compounds of antimony, lead, and other toxic metals whereas the relatively harmless ingredients include zinc and iron. The toxicity of the solvents varies from the very toxic benzene to the relatively non-toxic acetone. The maximum permissible safe concentrations for some of the solvents and pigment ingredients are listed in the table at the end of this chapter.

The important methods for controlling the health hazards of spray painting are: (1) the use of paints having relatively harmless solvents and pigments, (2) the use of mechanically exhaust-ventilated spray paint booths and rooms, (3) the use of suitable personal protective devices, and (4) good personal hygiene.

All spray paint booths and rooms should be mechanically

246 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

ventilated at rates given below and the discharge should in all cases be located at a point where the contaminated air will not reenter any building.

Spray painting should be done in mechanically exhaust-ventilated spray paint booths, preferably of the water curtain type. The painting operation should be an automatic one on all production work, if practicable. The object being painted should be supported by a jig or other suitable mechanical device and should be located well within the confines of the booth.

Small spray painting booths (those having face areas of less than 50 square feet) should have a minimum exhaust ventilation rate of 200 c.f.m. per square foot of face area of the booth, whereas a minimum of 150 c.f.m. per square foot of face area will suffice for larger booths. The air velocity should be essentially uniform across the entire face of the booth.

Downdraft exhaust ventilation through a grid type floor is advisable in booths or rooms where cars, trucks and other large objects are spray-painted. A minimum air velocity of 150 f.p.m. toward the grids should be maintained at the painting location. However for intermittent painting operations of this nature any well ventilated room is satisfactory if the worker wears at all times while in the room a supplied-air (air-line) respirator approved by the U. S. Bureau of Mines.

Wherever it is necessary for the painter to work downstream (as regards air movement) of the object being painted or if the object being painted is large so that the painter is exposed to the paint mist, he should wear a supplied-air (air-line) respirator approved by the U. S. Bureau of Mines. Also all painters who use spray guns for painting in the repair and construction of buildings and equipment should wear approved supplied-air respirators at all times while painting.

In rare instances for intermittent operations, it will be found to be more feasible to provide the sprayer with a supplied-air hood covering the entire head than to provide the large amount of ventilation necessary to control adequately the exposure. In such cases, the use of supplied-air hoods is permissible.

Good personal hygiene as given under brush painting (*Painting, Brush*) should be practiced.

Paint Manufacture, Camouflage (see Camouflage Paint Manufacture)

Pellet Density Testing

The principal health hazard associated with the tetryl pellet density testing operation is that of mercury vapor. The maximum allowable atmospheric concentration of mercury vapor for an eight-hour daily exposure is 0.1 mg./m.³

Although this operation is usually intermittent, any spilled mercury gives rise to a constant exposure. Good housekeeping is essential in the handling of mercury. Pellet density testing should not be done in areas adjacent to heated surfaces such as radiators or hot water pipes, and should preferably be done in areas having good general ventilation. The operations in density testing should be done on a large tray having a flanged edge and sloping to one corner containing a well. The mercury should be removed from the well frequently, and all mercury not in use should be kept in closed containers.

Pickling

The potential health hazards found in pickling are acid mists, acid gases, and gases liberated due to impurities either in the pickling acid or the metal being cleaned. The maximum allowable concentration in the atmosphere for some of these are:

Hydrogen chloride	10 p.p.m.
Hydrogen sulfide	20 p.p.m.
Sulfur dioxide	10 p.p.m.
Arsine	1 p.p.m.
Phosphine	1 p.p.m.
Nitrogen oxides	40 p.p.m.

The acid mists and gases liberated during pickling operations should be prevented from entering the room atmosphere by enclosing or partially enclosing the tank if possible and by providing mechanical exhaust ventilation at the enclosure. The rate of ventilation should be sufficient to produce an air movement into the enclosure of at least 100 f.p.m. at all openings. Where enclosure is not practicable, local exhaust ventilation should be provided at the tank by means of slot-type hoods at the upper perimeter of the tank. The minimum required ventilation rate will vary with the nature of the operations but should never be less than 120 c.f.m. per square foot of tank area. The exhaust system should be constructed of acid resisting material and the exhausted air should be discharged at a point where it will not reenter occupied buildings.

248 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

Pickling operators should wear acid-proof protective clothing and should practice good personal hygiene.

Pontoon (Rubber) Manufacture (see Rubber Goods Fabrication)

Primer Mixture Screening

The potential health hazards of primer mixture screening are the dusts from the various ingredients of the primer mixture. The maximum allowable concentration of lead thiocyanate in terms of lead is 0.15 mg./m.³ of air while the currently accepted maximum allowable concentration of TNT in the atmosphere is 1.5 mg./m.³. Although the maximum allowable concentrations of many of the primer mixture ingredients are not known, they should be kept as low as is possible with good engineering practice.

Screening of the various ingredients of the primer mixture should be done in an enclosed system. This may be accomplished by providing a tight-fitting cover for the screen, and either attaching the receptacle directly to the screen or using a flexible dust-proof sleeve to connect the receptacle to the screen. Since the exposure is intermittent and for only brief periods of time and since the workers on this job are usually rotated, the most practicable control method is personal respiratory protection. The respirators (mechanical-filter type) should be approved by the U. S. Bureau of Mines and should be cleaned and repaired daily by one individual who should be assigned to this task.

Printing (Cleaning Type and Presses)

The potential health hazards in printing operations are solvent vapors. Some of the solvents commonly used to clean type and presses are benzene, carbon tetrachloride, methyl alcohol, and trichlorethylene.

The maximum allowable atmospheric concentrations for an eight-hour daily exposure to these solvents are:

Benzene	100 p.p.m.
Carbon tetrachloride	100 p.p.m.
Methyl alcohol	200 p.p.m.
Trichlorethylene	200 p.p.m.

No cleaning compounds containing any considerable amounts of benzene, carbon tetrachloride, or methyl alcohol should be used; petroleum naphthas are preferred.

The printing room should be large and have good natural ventilation. Mechanical exhaust ventilation fans should be lo-

cated in roof ventilators if the room is small and the amount of work sufficient to raise the concentration of the solvents above the maximum allowable concentration.

Protectoscope Manufacture

In the manufacture of protectoscopes for tanks, a mirrored surface is coated with plexigum in ethylene dichloride. The maximum allowable concentration for ethylene dichloride is believed to be about 100 p.p.m. The exposures commonly encountered in these operations produce nausea and vomiting.

Owing to the nature of the operation, it is usually carried out in a room devoid of mechanical ventilation, and local exhaust ventilation likewise is impracticable because of the formation of bubbles on the mirrored surface. The exposures are usually of short duration and may be controlled effectively by the use of U. S. Bureau of Mines approved chemical-filter respirators (gas masks) for protection against organic vapors.

Rosin Melting (Melting Rosin for Filling Shrapnel Projectiles)

The health hazard in this operation is the exposure to decomposition products of the melted rosin at the temperature usually employed (400 to 450° F.). These products are acid in reaction and are very irritating to the mucous membranes of the operators.

The hazard should be controlled by partly enclosing the rosin melting pot and providing exhaust ventilation at the enclosure of not less than 100 c.f.m. per square foot of opening in the enclosure.

Rubber Boat Manufacture (see Rubber Goods Fabrication)

Rubber Goods Fabrication

The potential health hazard associated with the fabrication of rubber goods is the rubber or rubber cement solvent. Various solvents are used including carbon disulfide, benzene, toluol, xylol, carbon tetrachloride, methyl ethyl ketone, petroleum naphthas, and ethylene dichloride. The maximum allowable concentrations of these solvents vary from as little as 20 p.p.m. for carbon disulfide and 100 p.p.m. for benzene to as much as 1000 p.p.m. for the petroleum naphthas. Sometimes the petroleum naphthas contain such aromatics as trimethyl benzenes, ethyl benzenes, and other benzene homologues which serve to increase their toxicity.

250 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

Inasmuch as the solvents in the rubber cements may be unknown or may vary from lot to lot, the control measures must be based on the assumption that the solvent is benzene, unless it is known to be otherwise, in which case the control measures may be relaxed accordingly. The operations vary considerably and include cementing operations on benches, on the floor, or on large objects at work-bench height; coating materials in mechanically operated spreaders; and the like. The exposure at some of these operations may be controlled by providing good general ventilation of the workroom. For some operations in small rooms as much as 40 to 80 air changes per hour are needed. (The minimum required ventilation may be computed by the equation

$$Q = \frac{X}{m} \text{ described earlier in this chapter.})$$

However, in many instances, general ventilation does not suffice. In such cases, local exhaust ventilation should be used if practicable; otherwise, suitable respirators (supplied-air respirators approved by the U. S. Bureau of Mines) should be used. The type of local exhaust ventilation which should be employed will depend upon many circumstances. Ventilation through grilles in the tops of the work benches serves admirably if the material being fabricated does not cover the entire bench. If it does, lateral exhaust hoods along one or both sides of the bench may be employed. If neither bench top nor lateral exhaust ventilation is practicable, updraft ventilation through hoods located above but as close to the work as feasible may be satisfactory. In general, these operations vary sufficiently to make each a distinct problem which can be solved only by careful study of the operation. In any event, the quantity of air removed should be sufficient to provide a minimum velocity toward the exhaust hood of 100 f.p.m. at the source of contamination.

If the solvent odor persists, the actual exposures should be determined to decide whether additional ventilation is necessary or whether respirators must be used.

Sand Mixing and Screening

The potential health hazard associated with sand mixing and screening operations is silica dust. The maximum allowable concentration of free silica is 5 million particles per cubic foot of air as determined by the standard light field technique.

Inasmuch as dry sand mixing and screening operations produce an enormous amount of silica dust, these operations should

be enclosed as much as possible and provided with local exhaust ventilation. Owing to the large number of ways these operations are carried out, no specific type of exhaust ventilation system can be suggested. However, the dust is usually controlled successfully if the ventilation rate is such that the air velocity toward the exhaust inlet is about 250 f.p.m. at the source of dust production. Periodic dust counts should be made in the area adjacent to these operations to check the performance of the exhaust ventilation system.

The exhausted air should be passed through a suitable collector to remove the dust before the air is discharged to the outside. The discharge outlet should be so located that the air will not reenter the buildings and in no case should the air be recirculated into the workroom even if the dust collector appears to be efficient. The collector should be cleaned frequently and routinely and should be maintained in good working condition.

A local exhaust ventilation system may not be necessary if the sand mixing and screening operations are intermittent so that the average exposure of the worker to silica dust is low. In such instances, the operations should be isolated to avoid exposing other workers to the dust and the exposed workers should wear respirators approved by the U. S. Bureau of Mines for protection against silica dust.

Self-sealing Fuel Tank Manufacture (see Rubber Goods Fabrication)

Shell Case Manufacture

A potential health hazard from metal fumes is encountered in the melting of brass in the initial billet casting operation. These fumes may be relatively toxic if the brass contains considerable lead (cartridge brass seldom contains lead) or they may be largely zinc oxide fumes. The maximum allowable concentration for lead in the atmosphere is 0.15 mg./m.³ and for zinc oxide, 15 mg./m.³, based on an eight-hour daily exposure.

The exposure may sometimes be controlled adequately by good general ventilation whereas in many instances local exhaust ventilation through hoods located above the melting pots is necessary. The required ventilation rate varies tremendously, depending upon circumstances, but should be sufficient to remove all the contaminated air from the vicinity of the melting pot.

Shrapnel Projectile Loading (see Rosin Melting)

252 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

Smokeless Powder Cutting and Graining (see Nitrocellulose Cutting and Graining)**Soldering**

The potential health hazards associated with soldering operations are lead fumes and hydrogen chloride gas from the acid flux. The maximum allowable concentration for an eight-hour daily exposure to lead fumes in the atmosphere is 0.15 mg./m.³ and to hydrogen chloride gas, 10 p.p.m.

Control measures should consist of local exhaust ventilation, general ventilation, and the use of personal respiratory protective devices, according to the nature of the operation. All soldering sites should have good natural ventilation, if possible.

Continuous or production soldering operations require local mechanical exhaust ventilation for the removal of lead fumes and acid gas. The workbench should be equipped with a grille-top through which the air is exhausted at the minimum rate of 100 c.f.m. per square foot of grille area. In addition, the stove or heater for the iron should be enclosed on three sides in a hood which is exhaust ventilated at the rate of about 100 c.f.m. per square foot of opening in the hood. The exhausted air should be discharged to the outside atmosphere in such a manner that it will not reenter the building.

For intermittent soldering operation of a repair nature, good general ventilation will control the exposure adequately.

For all operations which are done in confined spaces, adequate ventilation should be provided by any suitable means such as a portable blower, fan, or air-operated ejector, or if this is impracticable, suitable respiratory protective devices should be worn. If an acid free flux is used, a mechanical-filter respirator approved by the U. S. Bureau of Mines for toxic dusts will suffice; otherwise, an approved supplied-air (air-line) respirator will be needed.

Spray Coating (see Painting, Spray)**Stenciling (see Painting, Spray)****Sulfation, Dimethylaniline (see Dimethylaniline Sulfation)****Sweetie Barrel Operation**

The principal potential health hazard associated with the sweetie barrel operation is dinitrotoluene in the form of dust,

fume, and vapor. While no maximum allowable atmospheric concentration has been established for DNT, it is believed to be of the same order of toxicity as TNT. The currently accepted maximum allowable atmospheric concentration for an eight-hour daily exposure to TNT is 1.5 mg./m.³

All weighing and sweetie barrel operations should be isolated insofar as it is practicable. Mechanical-filter respirators or supplied-air (air-line) respirators approved by the U. S. Bureau of Mines for protection against toxic dusts should be worn by the workers while scraping the insides of the sweetie barrels, and while holding the bags receiving the discharge from the sweetie barrels.

Tank (Aircraft Fuel) Manufacture (see Rubber Goods Fabrication)

Testing, Ballistics (see Ballistics Testing)

Tetryl Blending

The potential health hazard in tetryl blending is tetryl dust. Although no maximum allowable concentration has been established for tetryl dust in the atmosphere, the concentration of the dust should be maintained as low as possible within the limits of good engineering practice. It is suggested that the atmospheric concentration of tetryl be maintained below a value of 1.5 mg./m.³ wherever practicable.

During periods of filling and discharging of the blender, a dust-tight connection should be maintained between the tetryl screen and the blender, and a dust-tight sleeve should be attached to the discharge end of the blender and should extend to the bottom of, or be removably attached to, the receiving unit. If the sleeve extends to the bottom of the receptacle, it should be manipulated by hand to release the tetryl with a minimum of dusting.

If the above suggestions do not reduce the atmospheric concentration of tetryl dust below 1.5 mg./m.³, mechanical-filter respirators approved by the U. S. Bureau of Mines should be worn by the workers while in the blending room.

Tetryl Crystallization

The potential health hazards in the tetryl crystallization operations are benzene vapors and acetone vapors. The maximum allowable concentration for an eight-hour daily exposure to ben-

254 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

zene in the atmosphere is 100 p.p.m. and while no maximum permissible safe limit has been established for acetone, it is known to be relatively non-toxic.

A substitute for benzene should be used if possible and the necessary precautions should be observed in handling the substituted solvent.

If benzene is used, the process should be enclosed as much as possible and adequate mechanical local exhaust ventilation should be provided at the vacuum pan. The rate of air removal at the source of benzene vapors should be not less than 100 f.p.m.

Tetryl Drying

The potential health hazard in tetryl drying operations is tetryl dust which is generated during the loading and unloading of drying screens in the tetryl dry house. The concentration of tetryl dust in the atmosphere should be maintained as low as possible within the limits of good engineering practice. A maximum concentration of 1.5 mg./m.³ is suggested. See *Tetryl Blending*.

A system of mechanical local exhaust ventilation should be installed to remove tetryl dust generated during the drying screen loading and unloading operations. The system should be such that the air movement is at least 100 f.p.m. at all points of dust production. If the use of local exhaust ventilation is impracticable or inadequate, the workers should wear respirators approved by the U. S. Bureau of Mines for protection against toxic dusts.

Due precautions should be observed with regard to the collection of tetryl dust in the duct work of the ventilating system, and with regard to the disposition of the dust removed by the ventilating system. A wet type collector located as close as possible to the source of dust removal is suggested for filtering the dust from the air before it is discharged to the outside.

Tetryl Mixing with TNT

The potential health hazards in the mixing of tetryl with TNT are tetryl dust and TNT vapors and fumes. The currently accepted maximum allowable concentration of TNT in the atmosphere is 1.5 mg./m.³ and a maximum atmospheric concentration of 1.5 mg./m.³ is suggested also for tetryl. See *Tetryl Blending*.

The mixing process should be partially enclosed and controlled by a mechanical exhaust system which produces an air movement of at least 100 f.p.m. at the face of the hood opening.

Tetryl Packing

The potential health hazard in tetryl packing operations is tetryl dust. The tetryl concentration in the atmosphere should be maintained below 1.5 mg./m.³ wherever feasible. See *Tetryl Blending*.

Local exhaust ventilation should be applied near the chute discharge from the tetryl hopper to the tetryl boxes at the source of tetryl dust. The rate should be sufficient to prevent the escape of dust into the atmosphere; a minimum velocity of 200 f.p.m. at the source of dust production is suggested.

Tetryl Pellet Density Testing (see Pellet Density Testing)**Tetryl Pelleting**

The potential health hazard in tetryl pelleting operations is tetryl dust. The tetryl concentration in the atmosphere should be maintained below 1.5 mg./m.³ wherever feasible. See *Tetryl Blending*.

In most instances the only atmospheric exposure to tetryl dust in tetryl pelleting occurs during the filling of the pelleting hopper and cleaning of the pelleting machine. Since these operations are intermittent and brief, the workers may be adequately protected by the use of respirators approved by the U. S. Bureau of Mines.

Tetryl Reaming

The potential health hazard in tetryl reaming operations for fuzes is tetryl dust. The tetryl concentration in the atmosphere should be maintained below 1.5 mg./m.³ wherever feasible. See *Tetryl Blending*.

A mechanical local exhaust system should be installed to control the tetryl dust at its source. The rate of air movement should be at least 100 f.p.m. at the source of the dust.

Tetryl Screening

The potential health hazard in tetryl screening operations is tetryl dust. The tetryl concentration in the atmosphere should be maintained below 1.5 mg./m.³ wherever feasible. See *Tetryl Blending*.

To accomplish the best results and to insure safe working conditions, the entire screening process, including the charging and discharging, should be enclosed as much as possible and

256 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

provided with exhaust ventilation at a rate which will produce an air velocity into all openings of not less than 100 f.p.m. and should be about 300 f.p.m. at the openings or leaks at the screen where the dust is liberated with considerable velocity. The charging hopper and the receptacles should be attached to the screen by means of flexible dust-tight sleeves. The exhausted air should be conveyed to a wet collector located as close to the source of dust as possible and consideration should be given to keeping the duct work upstream of the collector free from tetryl deposits. Partial enclosure of the charging hopper with one side open for charging will aid in the prevention of atmospheric contamination at this point. At the discharges (both the coarse and fine outlets) the flexible dust-tight sleeve attached to the screen outlets should be permanently attached to a receptacle cover which may be transparent, if necessary. If this is not practicable, a ventilated canopy-type hood should be attached to the sleeve and located above but as close as possible to the receptacle. The minimum ventilation rate through the canopy hood should be 300 c.f.m. per square foot of opening between the receptacle and hood perimeter.

If the operation is intermittent or if exhaust ventilation is impracticable, the charging hopper should be entirely enclosed and provided with a door large enough to receive a box of tetryl and with a frame and crank such that a box of tetryl may be held in the frame and inverted by means of the crank outside the enclosure while the door is closed; also the hopper and receptacle should be connected to the screen by means of flexible dust-tight sleeves, and the workers should wear at all times while in the screening room mechanical-filter respirators approved by the U. S. Bureau of Mines for toxic dusts.

Tinning Process, Cold (see Cold Tinning Process)

TNT Break-Up (see Amatol Break-Up)

TNT Cooling

The operation in which tubs of liquid TNT are cooled to the desired temperature before pouring, presents an exposure to TNT vapor and fume. The maximum allowable safe concentration for atmospheric TNT is 1.5 mg./m.³

If the cooling tubs are stirred manually or if a number of tubs are cooling at the same time in a bay or room, the atmos-

pheric contamination in the room will be excessive. This condition may be prevented by (1) providing exhaust ventilation at each tub, or (2) ventilating the bay or room adequately. It is preferable that the tubs be stirred mechanically, but if each tub is ventilated properly, this is not essential.

Each tub may be ventilated adequately by installing a partially enclosing or a semicircular hood at the locations where the tubs are stirred so that when the tubs are in cooling position the enclosure or hood will be close to and almost adjoining the kettle. The recommended minimum exhaust ventilation rate for a hood is 120 c.f.m. per square foot of tub area and for a partial enclosure is 100 c.f.m. per square foot of opening in the enclosure. A suitable collector (preferably wet) should be located as close to the hoods or enclosures as possible so that the contaminated air is conveyed only a short distance in the duct work.

If local exhaust ventilation is impracticable, the contamination may be prevented from escaping into adjoining rooms by exhaust-ventilating the cooling bay or room at a minimum rate of 50 c.f.m. per square foot of opening into the bay. If general ventilation is used, the workers should wear U. S. Bureau of Mines approved mechanical-filter respirators at all times while in the cooling bay.

TNT Drying

The potential health hazard in TNT drying operations is TNT in the form of vapor and fume. The currently accepted maximum allowable concentration for TNT in the atmosphere is 1.5 mg./m.³

This operation should be completely enclosed to prevent the contamination of the atmosphere with TNT vapor. Provision should be made to exhaust the vapor from the drier to the outside atmosphere.

TNT Flaking

The potential health hazard in TNT flaking operations is TNT in the form of vapor, dust and fume. The currently accepted maximum allowable concentration of TNT in the atmosphere is 1.5 mg./m.³

The flaking machine should be partially enclosed and mechanically exhaust-ventilated at a rate sufficient to produce a velocity into the enclosure of at least 150 f.p.m. at all openings.

258 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

TNT Graining

The potential health hazard in TNT graining operations is TNT vapor and dust. The currently accepted maximum allowable concentration for an eight-hour daily exposure to TNT in the atmosphere is 1.5 mg./m.³

Each graining kettle should be enclosed completely by a hood which has an observation lid that may be opened; the hood should be exhausted mechanically at a rate sufficient to produce an air velocity of at least 100 f.p.m. at the hood face when the observation lid is open. All contaminated air should be discharged to the outside atmosphere in such a manner that it will not reenter the building.

TNT Melting

The potential health hazard in TNT melting operations is TNT vapor, fume and dust. The currently accepted maximum allowable concentration for an eight-hour daily exposure to TNT is 1.5 mg./m.³

The melting kettles should be enclosed and should be mechanically exhaust ventilated. The enclosure should be provided with the necessary number of lids or access doors which may be opened. The exhaust ventilation rate should be such that the air movement at the hood face when one lid is open is not less than 100 f.p.m.

In filling the TNT hoppers above the melting units, precautions should be observed to create as little dust as possible. If these hoppers are of good design and the charging is done properly, no atmospheric dust hazard should exist. However, if the concentration of TNT in the atmosphere during the filling operation exceeds 1.5 mg./m.³, the workers should wear respirators approved by the U. S. Bureau of Mines.

TNT Metal Tub Cleaning (see also Amatol Bucket Cleaning)

The potential health hazard in TNT metal tub cleaning operations is TNT dust. The currently accepted maximum allowable concentration of TNT in the atmosphere is 1.5 mg./m.³

For intermittent operations, mechanical-filter respirators approved by the U. S. Bureau of Mines should be worn by workers engaged in metal tub cleaning.

For continuous operations, the work should be done in mechanically ventilated exhaust booths which have a face velocity of not less than 200 f.p.m. and the operator to avoid excessive

exposure should remain upstream of the tub at all times while cleaning. The exhausted air should be discharged at a point on the outside where it will not reenter the buildings. Consideration should be given to the safety hazard associated with the collection of TNT dust in the ductwork; a wet collector close to the booth is suggested.

TNT Pouring and Puddling (see Amatol Pouring and Puddling)

TNT Purification

The potential health hazard in TNT purification operations is TNT vapor and fume. The currently accepted maximum allowable concentration of TNT in the atmosphere is 1.5 mg./m.³

The TNT purification process should be entirely enclosed to prevent the contamination of the workroom atmosphere.

TNT Screening

The potential health hazard in TNT screening operations is TNT dust. The currently accepted maximum allowable concentration of TNT in the atmosphere is 1.5 mg./m.³

As a rule, TNT screening operations require local exhaust ventilation to maintain safe working conditions. The hopper from which TNT is fed onto the screen should be partially enclosed with an open face hood to permit filling of the hopper. The hood should be mechanically exhausted so that the hood face velocity will be at least 100 f.p.m. Care should be taken in filling the hopper to disseminate as little TNT dust as possible into the room atmosphere.

The connection between the hopper and the screen should be dust-tight at all times. Dust-tight sleeves or boots should be used between the screen outlet and the receiving unit; this applies to the coarse material discharge as well as to the screened TNT. These sleeves may either be attachable to the top of the receptacles by means of dust-tight connections or extend to the bottom of the receptacles to prevent the escape of dust into the atmosphere.

The screen should be enclosed, mechanically operated and mechanically ventilated, if necessary. The ventilation rate should be such that the air velocity at all openings is not less than 300 f.p.m. All contaminated air should be discharged to the outside atmosphere in such a manner that it cannot reenter the room.

Wherever the TNT dust concentration exceeds 1.5 mg./m.³

260 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

in the workroom atmosphere, workers exposed should wear mechanical-filter respirators approved by the U. S. Bureau of Mines.

Toluene Nitration

The potential health hazards associated with the nitration of toluene are toluene, nitrogen oxides, mononitrotoluene, dinitrotoluene, and TNT. The currently accepted maximum allowable concentrations of these substances for an eight-hour daily exposure are as follows:

Toluene	200 p.p.m.
Nitrogen oxides	40 p.p.m.
Mononitrotoluene	Similar to nitrobenzene, which is generally 5 p.p.m.
Dinitrotoluene	Similar to TNT
TNT	1.5 mg./m. ³

All toluene nitrators should be enclosed and connected to an acid recovery plant by means of a local exhaust ventilation system. The nitrators should be held under a sufficient negative pressure to prevent the escape of nitrogen oxides into the room atmosphere during the nitration operation. As an additional protective measure, an auxiliary exhaust system should be installed on all nitrators for use in case of a breakdown or overloading of the regular exhaust system.

The observation section of the drain pipe leading from the nitrator should also be provided with local exhaust ventilation to prevent escape of nitrogen oxides and other toxic materials into the room atmosphere during the separating operation.

Tracer Bullet Charging

The potential health hazards in the charging of copper jackets with tracer mixture and igniter mixture are the tracer and igniter mixture dusts and the solvent vapors (carbon tetrachloride and methyl alcohol) resulting from the removal of the dusts from the charging machines and from the washing of the dies. The maximum allowable concentration of tracer mixture and primer mixture are not known but it is believed that no harm will result to the workers if the total dust concentration is kept below 5.0 mg./m.³ and the barium peroxide concentration below 0.5 mg./m.³. The allowable concentration of carbon tetrachloride in the atmosphere is 100 p.p.m. while that for methyl alcohol is 200 p.p.m.

General room ventilation should be provided to keep the tracer and igniter mixture dust in the air near the charging machines

and in the breathing zone of the workers below the allowable limit. Mechanical air conditioning with sufficient air changes per hour should be satisfactory if the air is not recirculated. If recirculation of part of the air is necessary, an efficient collector for both the dusts and vapors is necessary in the conditioning system to remove the contaminating materials from the air before recirculation. All charging machines should be cleaned at least once an hour, and oftener, if necessary. Air blowing of the dust on the machines should not be permitted; a commercial vacuum cleaning apparatus with an efficient filter should be used. Trichlorethylene, ethyl alcohol and coal oil should be used for wiping the machines and cleaning the dies; the use of carbon tetrachloride and methyl alcohol should be avoided.

Tracer Mixture Blending

The potential health hazard during tracer mixture blending operations is tracer mixture dust. Although the specific maximum allowable concentration of tracer mixture dust has not been determined, it is believed that the total amount of this dust in the workroom atmosphere should not exceed 5.0 mg./m.³

A flexible dust-tight sleeve or boot should be attached to the outlet of the blender and should either be attachable to the top of the receptacle by means of a dust-tight connection or extend to the bottom of the receptacle so that the dust created in the fall is not permitted to escape into the workroom atmosphere. With the latter arrangement, the sleeve should be manipulated by hand and care should be taken to avoid any unnecessary disturbance which would disseminate dust into the air. If the total tracer mixture dust content in the air exceeds 5.0 mg./m.³, the workers should wear mechanical-filter respirators approved by the U. S. Bureau of Mines. This may be necessary, particularly when charging the blender. The operators should practice good personal hygiene and good housekeeping.

Tracer Mixture Screening and Mixing

The potential health hazards of the tracer mixture screening and mixing operations, when conducted in the same room, are tracer mixture constituent dusts and carbon tetrachloride vapor. The maximum allowable concentration for carbon tetrachloride in the atmosphere is 100 p.p.m. Although the specific maximum allowable concentration for tracer mixture dust in the atmosphere has not been determined, it is believed that the total amount

262 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

of this dust in the workroom atmosphere should not exceed 5.0 mg./m.³

If possible, precipitated calcium resinate should be used in the preparation of tracer mixture, thereby eliminating the necessity of using carbon tetrachloride. If carbon tetrachloride is used, all of the air contaminated with the carbon tetrachloride vapors should be exhausted directly to the outside atmosphere.

Dust producing operations should be done in mechanically exhaust-ventilated hoods which have a minimum face area consistent with proper performance of the operations. The average hood face velocity for the control of operations which produce only a slight amount of dust may be as low as 100 f.p.m. but the average hood face velocity at very dusty operations should be not less than 150 f.p.m. In all instances, the hood design should be such that the necessary minimum control velocities exist in the zone of dust production.

Welding (Oxyacetylene and Electric)

The potential health hazards found in oxyacetylene and electric welding are fumes, gases, and infra-red and ultraviolet radiation. On some welding or cutting operations, such as the repair of ships or other painted structures, severe exposures to lead may result from the paint, or to mercury if mercury containing anti-fouling paint had been used. Also where welding rods having fluoride fluxes are used, there is an exposure to hydrogen fluoride and volatile fluoride salts. The maximum allowable concentrations on the basis of eight hours' daily exposure for some of the substances which may be encountered are:

Mercury	0.10 mg./m. ³
Lead	0.15 mg./m. ³
Hydrogen fluoride	3 p.p.m.
Nitrogen oxides	40 p.p.m.
Zinc oxides	15 mg./m. ³

Welding sites should be isolated from nearby workers by the use of screens or shields which protect the surrounding workers from the injurious light rays. At the same time these shields should not be more enclosing than necessary lest the ventilation at the welding site be reduced more than is desirable. Goggles, shields or helmets and other necessary protective clothing should be worn by the welders to protect their eyes and skin from the infra-red and ultraviolet radiation given off while welding.

The fume and gas hazard may be controlled by (1) ventila-

tion, and (2) personal protection. Wherever practicable, local exhaust ventilation should be employed and in other cases either general ventilation alone or general ventilation supplemented by respiratory protective devices is necessary. On routine operations, at more or less permanent locations or in places where continuous welding is done and conditions permit, local exhaust ventilation should be provided. For those operations where the welder moves about, a 3- or 4-inch flexible metal hose may serve as the hood and exhaust duct. Some systems are available also in which the flexible hose is counterweighted and the terminal end or hood is readily adjustable to any location. The minimum amount of air which must be exhausted from each welding operation is 250 c.f.m. and may be as high as 1,200 c.f.m. where large amounts of fumes and gases are produced. The exhaust hood should be kept as close to the operation as possible and should never be more than 12 or 15 inches away.

If welding is done in the open, natural ventilation is usually sufficient to prevent a health hazard. When welding in small enclosed spaces, the welder should wear an approved respirator of the supplied-air type (air-line) if adequate local exhaust ventilation is impracticable.

In many types of resistance welding, for example, seam and spot welding, ultraviolet and infra-red rays are not produced. However, welding fumes and gases are produced. If the amounts of toxic material in the atmosphere near such operations exceed the maximum permissible safe concentrations, and if workers are located in these areas, sufficient local exhaust ventilation should be provided to control the hazard.

Wood Veneer Processing

In the manufacture of airplane wings, propellers and other similar products from laminated wood, the component parts are dipped in phenolic resins which are heated and subjected to pressure. In such operations, there is a potential exposure to high atmospheric concentrations of phenolic resins unless appropriate control measures are observed. The maximum allowable concentration of this material has not been determined, but it is known to be quite toxic.

The dipping operation should be carried out in an exhaust-ventilated spray booth similar to a spray-painting booth. The ventilation rate through the booth should be not less than 100 c.f.m. per square foot of booth opening.

264 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

TABLE 3.—TOXIC LIMITS OF VARIOUS SUBSTANCES

<i>Substance</i>	<i>Maximum Allowable Concentration*</i>
Acrolein.....	1 p.p.m.
Acrylonitrile.....	20 p.p.m.†
Ammonia.....	100 p.p.m.
Amyl acetate.....	400 p.p.m.†
Aniline.....	5 p.p.m.
Arsine.....	1 p.p.m.
Benzene (Benzol).....	100 p.p.m.
Butyl acetate.....	400 p.p.m.†
Butyl alcohol.....	200 p.p.m.†
Carbon dioxide.....	5000 p.p.m.
Carbon disulfide.....	20 p.p.m.
Carbon monoxide.....	100 p.p.m.
Carbon tetrachloride.....	100 p.p.m.
Dichlorobenzene.....	75 p.p.m.
Dimethylaniline.....	similar to aniline
Ethylene dichloride.....	100 p.p.m.
Gasoline (Petroleum).....	1000 p.p.m.
Hydrogen chloride.....	10 p.p.m.
Hydrogen cyanide.....	20 p.p.m.
Hydrogen fluoride.....	3 p.p.m.
Hydrogen sulfide.....	20 p.p.m.
Methyl alcohol.....	200 p.p.m.
Monochlorobenzene.....	75 p.p.m.
Mononitrotoluene.....	similar to nitrobenzene
Nitrobenzene.....	5 p.p.m.
Nitrogen oxides.....	40 p.p.m.
Petroleum naphthas.....	1000 p.p.m.
Phosgene.....	1 p.p.m.
Phosphine.....	1 p.p.m.
Sulfur dioxide.....	10 p.p.m.
Tetrachloroethane.....	10 p.p.m.
Tetrachloroethylene.....	200 p.p.m.
Toluene (Toluol).....	200 p.p.m.
Trichlorethylene.....	200 p.p.m.
Turpentine.....	200 p.p.m.
Xylene (Xylol).....	200 p.p.m.
Barium peroxide.....	0.5 mg./m. ³ †
Cadmium.....	0.1 mg./m. ³
Chromic acid.....	0.1 mg./m. ³
Lead.....	0.15 mg./m. ³
Mercury.....	0.1 mg./m. ³
Dinitrotoluene.....	similar to TNT
Tetryl.....	1.5 mg./m. ³ †
TNT.....	1.5 mg./m. ³
Zinc oxides.....	15.0 mg./m. ³
Silica (SiO ₂) (free or uncombined).....	5 m.p.p.c.f.

* The maximum allowable concentration for the various substances listed are the values most widely accepted today and are based on an eight-hour daily exposure.

† These values have not been definitely established but are included to serve as a guide.

‡ No specific information available, but believed to present no health hazard at this concentration.

Note: p.p.m. = Parts of substance per million parts of air by volume.

mg./m.³ = Milligrams of substance per cubic meter of air.

m.p.p.c.f. = Millions of particles of substance per cubic foot of air.

TABLE OF TOXIC LIMITS

From time to time, it is necessary for industry to change from one material or substance to another for one of several reasons, such as scarcity of materials, improvement of product, change in process, or reduction in the health hazard. When this becomes necessary, it is important that a substance be selected which is less toxic than the former substance. Whereas the relative toxicity of many materials is unknown at present, there is presented in Table 3 a list of substances and their relative toxicities. This table will be found useful as a guide in the selection of less toxic substitutes.

ACKNOWLEDGMENT

The author expresses appreciation for the valuable assistance in collecting and assembling the information contained in the section on *Specific Control Measures by Operation*, and in the *Table of Toxic Limits*, given by P. A. Industrial Hygiene Engineer (R) J. E. Flanagan, Jr., Assistant Sanitary Engineer (R) T. E. Shea, Assistant Sanitary Engineer (R) Lester V. Cralley, and Assistant Sanitary Engineer (R) Lewis J. Cralley.

BIBLIOGRAPHY

1. Fundamentals Relating to the Design and Operation of Exhaust Systems. ASA Code Z9. American Standards Association, New York, 1936.
2. National Institute of Health, Division of Industrial Hygiene: Benzene (Benzol), Its Toxicity and Potential Dangers. U. S. Pub. Health Rep., 56:519 (March 14) 1941. Reprint No. 2248.
3. Russell, A. E., et al.: Lead Poisoning in a Storage Battery Plant. U. S. Pub. Health Bull. No. 205. Government Printing Office, Washington, D. C., 1933.
4. Neal, P. A., et al.: Mercurialism and Its Control in the Felt-Hat Industry. U. S. Pub. Health Bull. No. 263. Government Printing Office, Washington, D. C., 1941.
5. Russell, A. E., et al.: The Health of Workers in Dusty Trades. U. S. Pub. Health Bull. No. 187. Government Printing Office, Washington, D. C., 1929.
6. DallaValle, J. M.: Principles of Exhaust Hood Design. U. S. Public Health Service, Washington, D. C., 1939. (Mimeographed.)
7. Safety in Electroplating Operations. ASA Code Z9.1-1941. American Standards Association, New York, 1941.
8. Brandt, Allen D.: Ventilation of Plating Tanks. Heating, Piping and Air Conditioning, 13:434 (July) 1941.
9. Alden, J. L.: Design of Industrial Exhaust Systems. The Industrial Press, New York, 1939.
10. Kravath, F. F.: An Outline of Industrial Exhaust Ventilation. Heating and Ventilating, 39:36 (April) 1942.

266 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

11. Hemeon, W. C. L.: Air Dilution in Industrial Ventilation. Heating and Ventilating, 37:39 (November) 1940.
12. Brown, C. E.: Respiratory Protective Devices. Jour. Ind. Hyg., 19:95 (February) 1937.
13. Schrenk, H. H.: Testing and Design of Respiratory Protective Devices. Information Circular 7086. Department of the Interior, Washington, D. C., 1939.
14. The Use and Care of Respirators. Air Hygiene Foundation of America, Pittsburgh, 1938.
15. American Standard for Grinding, Polishing, and Buffing Equipment Sanitation. ASA Code Z43-1941. American Standards Association, New York, 1941.
16. Grinding Wheels. Safe Practices Pamphlet No. 13. National Safety Council, Inc., Chicago, 1938.
17. U. S. Department of Commerce, National Bureau of Standards: Safe Handling of Radioactive Luminous Compound. National Bureau of Standards Handbook H27. Government Printing Office, Washington, D. C., 1941.
18. U. S. Department of Commerce, National Bureau of Standards: Radium Protection. National Bureau of Standards Handbook H23. Government Printing Office, Washington, D. C., 1938.

CHAPTER 12

MEDICAL CONTROL OF RESPIRATORY DISEASES

W. C. Dreessen, M.D.

THE PROBLEM

TODAY, as never before, the comparative lack of specific control measures and the terrific toll of the respiratory diseases—colds, influenza, pneumonia, and tuberculosis—are making rigid demands upon the acumen of every industrial physician, and at the same time cast out a challenge to preventive medicine which cannot be ignored. Fully one-half of the sick absenteeism and over one-third of the work days lost by industrial workers through disability are attributable to respiratory disease. The strategic position of the plant physician for the control of these diseases is not as favorable as it is in the case of such diseases as malaria and syphilis for which specific chemotherapeutic agents are available or in the case of smallpox against which active immunity can be attained.

Workplaces not infrequently provide many of the predisposing factors regarded as significant in respiratory infections. Many workers for the first time in their lives are coming face to face with such conditions as a relatively crowded environment and exposure to gases, fumes, and dust. They must contend with occupational fatigue in becoming hardened to a new form of work. Many are exposed to inclement weather and extreme changes in weather conditions. Malnutrition, allergy, alcoholism, personal handicaps, and other factors contribute to the decreased ability of the individual to resist infection.

It is the purpose of this chapter, first, to review certain measures as they pertain to the control of acute respiratory diseases, and second, to outline similar measures as they apply to tuberculosis and other chronic pulmonary diseases in industry.

ACUTE RESPIRATORY INFECTIONS

The acute respiratory infections are a heterogeneous group of ailments caused by various agents. It is highly probable that many of the so-called colds are caused by filterable viruses. More

268 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

than thirty types of pneumococci are involved in pneumococcal pneumonia; more than two types of viruses are known to cause epidemic influenza. The filterable viruses are particularly likely to initiate the disease process. Moreover, it is now recognized that the common pathogens of the respiratory tract participate in the pathogenesis of acute respiratory syndromes. Only too frequently is the common cold followed by such formidable sequelae as pneumonia and tuberculosis.

Prevalence of Colds

The extensive studies by the U. S. Public Health Service and other organizations have contributed many important facts regarding the common cold. Since it is obviously impossible to present a complete review, only certain etiologic and epidemiologic features will be stressed. The attack rate per person usually averages 2 to 3 per year. Almost all persons are susceptible and very few persons avoid an attack of acute respiratory infection during the course of any one year. Townsend,¹ for instance, stated that in a group followed for 5½ months 90 per cent reported one or more attacks. There is typically, but not always, a period of high prevalence in early spring, a decline in midsummer, another period of high prevalence in autumn, and some decline in December. The peak in the fall of the year is reached with almost explosive suddenness and a high incidence will usually be reported simultaneously in all sections of the country.

Gover, Reed, and Collins,² studying data from students in various universities in the United States over a period of 18 months, concluded that there is "no definite association of respiratory attack rate with marked variations in climate as represented by six American cities with wide geographic and climatic differences."

Other investigators³ have also failed to observe a consistent relation between the incidence of colds and latitude, longitude, and climate.

The above conditions apply to continental United States, but, lest we overlook the infectious nature of colds, the Spitzbergen observations⁴ may be recalled. Spitzbergen is comparatively free of colds in winter, but with the opening of the shipping season about three-fourths of the community's population suffer an attack of the common cold within a week following the arrival of the first ship. Similar observations, as well as clinical and experimental investigations, indicate that the incubation period

for the common cold is probably between 12 and 48 hours or possibly as long as 72 hours.

Cold Vaccine

Prophylactic immunization against the common cold has been tried by means of filterable virus vaccine and by vaccines prepared from mixtures of various pathogens of the respiratory tract. The virus vaccine has had only limited trial and has not proved to be efficacious. According to Dochez,⁵ the future value of common cold virus vaccine is problematical because an attack of cold gives little or no immunity. Bacterial vaccines containing a variety of respiratory pathogens have been used on a wide scale. Many industrial physicians have had first-hand experience with them.⁶ The stock vaccines contain killed pneumococci, *H. influenzae*, *M. catarrhalis*, staphylococci, and streptococci. These organisms tend to be present in the normal nasopharyngeal flora and in case of an attack are assumed to act as secondary invaders. As a result of using such vaccines one would expect a lessening in the harmful effect of these organisms. According to some authorities, these secondary invaders play an important role in a small group of adults who suffer each year from prolonged infections of the upper respiratory tract with such complications as sinusitis and bronchitis. For theoretical reasons, some believe that such vaccines are of considerable value if restricted to that group of individuals in which secondary bacterial infection presumably plays an important part. *The use of these vaccines, however, has not received the endorsement of public health workers, mainly because of lack of scientific proof.*

Influenza Prophylaxis

The etiologic agent of certain epidemics of influenza, as in the instance of the common cold, is a filterable virus. Influenza occurs mainly in a pandemic, an epidemic, or an endemic form.⁷ The cause of pandemic influenza, such as occurred in 1918-1919, is not yet known. In the epidemic form, at least three filterable viruses have been isolated. The cause of endemic influenza, or sporadic grippe is also undetermined. In influenza such organisms as *H. influenzae*, streptococcus, pneumococcus, and *M. catarrhalis* are regarded as secondary invaders which aggravate the pathologic picture by frequently inducing severe and fatal bronchopneumonias. Immunization would be an ideal method of prevention, but no efficacious procedure has been available in past

270 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

epidemics, probably as the cause had not been fully determined. "Individual immunity to the virus of influenza as measured by the development of neutralizing antibodies in the blood can be readily accomplished by inoculation of human beings with either living or killed cultures of influenza virus."⁶ Extensive studies are now being carried out with different antigenic strains of the virus. A flu-distemper viral vaccine has been used recently.⁷ Horsfall⁸ in his recent review, however, concludes that the average extent of immunity induced by vaccines containing influenza A virus was too insufficient to allow it to be considered as a practicable prophylactic measure.

Pneumonia Prophylaxis

Artificial immunization against lobar pneumonia, whether active or passive, is of questionable value for prevention. It is known that immunity develops to pneumococci, but the duration of the immunity thus induced is limited.

Environmental Control

Besides control along immunologic lines, measures directed at environment have recently been receiving increased attention. The new "air-borne" or indirect hypothesis "postulates that the greatest spread of respiratory infection is produced by small dried droplets floating in air for relatively long times and distances or by the resuspension of dried droplets in air after they have settled to surfaces such as floors, clothing, and bed clothes."⁹ Alpha hemolytic streptococci of nasopharyngeal origin are widely distributed. The virulence of the microorganism is never more than slightly impaired by sojourn in rooms. One of the outgrowths of these observations as related to surgery is that it has been possible to reduce wound infections by less frequent dressings.

The object in environmental control is to destroy the respiratory pathogens in air either by radiation, or by chemical sprays or aerosols. It has been observed that the concentration of organisms in the air is reduced by natural sunlight; even diffuse daylight has been found to have a lethal effect. These observations suggest planning for maximum window space in occupied buildings.

Ultraviolet radiation, while more potent than visible light, cannot, at present, be unreservedly endorsed for use in industrial plants for the purpose of controlling acute respiratory infections.

If it is used, special attention must be given for protection of individuals, particularly as regards exposure of skin and eyes.

Aerosols.—Various germicides in an appropriate solvent and sometimes incorporating a wetting agent have been used as aerosols. Among the various agents that have been used in experimental work are resorcinol, resorcinol glycerine, hexyl resorcinol in propylene glycol, formaldehyde-water, and hypochlorite solutions. Twort and his coworkers¹⁰ found that 10 per cent hexyl resorcinol dissolved in propylene glycol added to 0.05 per cent sulfonated lorol was the most effective all-around germicidal mixture of those they tested. Minimal effective mist concentration of resorcinol glycerine aerosol was about 1:400,000,000 by volume. This level was confirmed by Williamson and Gotaas.¹¹ The latter, in referring to the practical use of aerosols in places occupied by persons, state that the aerosol must be nontoxic to man, nonirritating to the eyes and lungs, rapidly lethal to the bacteria when present in small concentrations, inodorous, invisible, non-inflammable, noncorrosive, persistent, and should not leave films and coatings on walls and furniture. Needless to say, considerable investigation is necessary before aerosols can be used in occupied rooms. It may be used in such rooms as laboratories and media rooms where the aerial germicide may be allowed to dissipate before the room is occupied.

General Measures in the Control of Colds, Influenza, and Pneumonia

Since no satisfactory immunity can be established against these acute respiratory infections and even the new chemotherapeutic agents are of little avail in viral pneumonias and most other viral diseases, it is apparent that many procedures are necessary to cope with an epidemic of one or all of these diseases. Specific measures of hygiene and sanitation are to be recommended during epidemic periods. Such measures have been tersely summarized for these respiratory diseases, as well as other communicable diseases, in a report of a committee of the American Public Health Association.¹² This pamphlet should be in the hands of every plant medical director.

Because the minor and acute respiratory ailments, such as common cold, not infrequently lead to disabling pneumonia, otitis media, and mastoiditis, a major effort should be directed toward controlling colds. Remembering that colds are spread by close contact in the acute stages of the disease, certain public

272 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

health procedures should be seriously considered. These include, among others, (1) isolation at home during the early and highly contagious stage of a cold which will lessen the spread of the infection, and (2) avoidance of close contact with persons suffering from colds, and of closed spaces where large numbers of infected persons congregate, which may be recommended through a health education program.

The spread of these diseases most frequently takes place through the medium of infected particles sprayed into the air by talking, coughing, and sneezing. Where general public health measures for control have been applied, they have included improvement of general hygiene and living conditions, especially overcrowding. Persons suffering from minor respiratory infections should take unusual care in the avoidance of dangerous contacts, allow themselves periods of rest, and avoid such predisposing factors as chilling, exposure to severe climatic changes, fatigue, and excesses of all kinds.

Many procedures in the plant medical department if adopted as routine may aid materially. The preemployment examination should pick out those prone to acute exacerbation, sinusitis, asthma, and bronchitis. Employees should be required to check through the medical department when they become ill on the job and after acute illness. These checks afford an excellent opportunity for directing those ill to prompt treatment by the new therapeutic techniques now available. Contact between persons in the more contagious phases of minor respiratory diseases can therefore be avoided. By thus encouraging prompt treatment, disabling effects may be reduced in number and severity. That an all-around industrial hygiene program will yield substantial results is attested to by a number of recent reports by industrial physicians.

CHRONIC RESPIRATORY INFECTIONS

In addition to the acute respiratory diseases, those of a chronic nature exact a large toll of lost time. These diseases are exemplified by pulmonary tuberculosis, which claims the lives of sixty thousand Americans each year. It is more and more becoming recognized as an affliction of older occupied men.¹³ As an example of American industrial tuberculosis experience, it is gratifying to note that the death rate¹⁴ among industrial policyholders of the Metropolitan Life Insurance Company has been reduced to about one-fifth that of 1917. With the changeover to

war production, however, attention must be directed to a possible increase of this disease, particularly as regards women. The single exception to a satisfactory public health situation in Britain was a rise of almost 10 per cent in the mortality from tuberculosis in 1939 and 1940.¹⁵ The increment in this case was greatest in young women and was thought to be related to malnutrition.

Control Programs

By directing medical measures for the control of the chronic respiratory diseases at pulmonary tuberculosis, tangible results are obtainable with nontuberculous affections as well. The essence of the medical program is the radiographic examination of the chest. This procedure has been the basis of medical control of silicosis, in which disease the infective element, particularly tuberculosis, is the principal cause of disability. As in pneumoconiosis, X-ray examination of the chest, if supplemented by clinical study, will aid in obtaining proper medical management for such other pulmonic conditions as bronchiectasis, asthma, and cancer.

As an illustration of what can be accomplished in tuberculosis control by a plant, reference is made to the experience of Sawyer.^{16, 17} An X-ray survey of 3,280 apparently healthy employees in 1921 showed 2.3 per cent positive for clinical tuberculosis. From 1928 on, the medical department has been doing serial or annual X-rays of the chest. In a group of 4,665 employees, averaging 33 years in age, and studied from 1928 to 1935, only 0.5 per cent showed active or clinical tuberculosis. By 1940 this percentage was down to 0.2 per cent, which is probably close to the irreducible minimum. What has been done by Sawyer can to a considerable extent be achieved in any employed group if a definite program is outlined and followed.

The Metropolitan Life Insurance Company,¹⁸ following the adoption of a tuberculosis control program, reduced the number of cases of significant pulmonary tuberculosis from 40 per 10,000 employees in 1930 to 10 per 10,000 in 1939. Use was made of routine preemployment X-rays and the Metropolitan sanatorium. It was observed, however, that during the period, 1930 to 1939, the prevalence of tuberculosis among applicants for employment had not been reduced; the experience indicates 80 cases of significant tuberculosis per 10,000 applicants and, according to Sherman,¹⁹ this probably represents a fair average.

274 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

Other industries also have had anti-tuberculosis programs in effect. There should be no relaxation in the program of controlling pulmonary infection and indeed an extension of the program to the smaller industrial plants is indicated.

X-ray Methods.—Recent radiographic surveys of employed groups, who had not been X-rayed previously, have revealed 1 to 2 per cent of the employees with significant tuberculosis. Case finding is an important feature in a tuberculosis control program that can be effected by the industrial physician. A number of X-ray procedures are available, such as single or stereo 14 by 17 inch films, 14 by 17 inch paper, 35 mm., 4 by 5 inch, or 4 by 10 inch photofluorographic methods, and fluoroscopic examination.

Photofluorograms have been adapted for mass X-raying work in the armed forces, as well as in the medical departments of a number of large industrial plants. If a grid is used, very satisfactory photofluorograms can be obtained. For best results this will require at least 200 milliamperes equipment. It has been the practice not to rely on the fluorograms, particularly the 35 mm. size, for diagnoses, but, instead, this technique is expected to pick out persons with definitely abnormal or suspicious chest findings. These individuals are then rechecked with standard 14 by 17 inch single or stereoroentgenograms taken for diagnostic interpretation.

In advocating small film X-ray pictures as a routine for all patients admitted to general hospitals, Hilleboe²⁰ refers to the experience of the University Hospital, Ann Arbor, Michigan, where it was found by this technique that 10 per cent of the patients admitted showed lesions of the organs in the chest. The U. S. Public Health Service now has eleven photofluorographic units in the field, each accompanied by a medical officer, technician, and clerk. Plants may appeal to the Public Health Service through the State health department for the services of one of these 35 mm. units if no other means for mass X-raying is available. Experience has shown that 300 to 500 photofluorograms a day can be made with one of the units.

Administrative Procedures.—Sawyer,^{16, 17} who has had years of experience administering a tuberculosis control program, offers helpful suggestions in its conduct. His program is directed at three groups: (1) applicants for employment, (2) employees with negative X-rays, and (3) employees with suspected tuberculosis. He has noted that it has been too time-consuming to furnish each individual a report on the findings yielded by his radiogram. Hence, he recommends issuing a mimeographed statement

to the patient at the time of X-ray, stating that if his X-ray is negative he will not receive a report, but if his lungs are affected he will be so notified. Employees having latent, clinically insignificant lesions are reported as having lungs that are negative or clear.

Employability.—Applicants with healed primary tuberculosis or inactive types of reinfection tuberculosis are ordinarily acceptable for employment. For a number of years the Public Health Service has advocated, even in the dusty trades, that the worker with evidence of healed primary tuberculosis should not be denied employment on this account alone. There are many types of employment where persons are acceptable with clinically negative, stabilized lesions, minimal or moderately advanced in extent. If adequate X-ray equipment is available, it may be possible in some instances to accept individuals with small soft lesions, but these workers will require close medical supervision. The individuals with active and questionably active tuberculosis are not acceptable for employment, but should be referred to their physician, the local public health authorities, or a clinic.

Frequency of Periodic X-Ray.—The means toward the end of obtaining satisfactory periodic X-rays is an adequate record system. This will make it possible to call back the employee for reexamination, according to the need for recheck. The Public Health Service has recommended annual medical examination of workers in the siliceous dusty trades to detect evidence of pulmonary tuberculosis and early silicotic changes. Sawyer²¹ recommends annual X-ray for young workers (ages 18 to 25), whose preemployment X-ray was negative for clinical tuberculosis, gradually increasing the time interval between examinations to three years if the chest roentgenogram continues to be negative. Individuals 30 years of age and over with negative X-rays at the beginning of employment are scheduled for re-X-ray at 3-year intervals.

The frequency of X-raying workers with evidence of tuberculosis depends on the extent of pulmonary involvement and dynamic status of the disease. Sherman.¹⁹ in the instance of ex-patients, has suggested X-ray and sputum study every three months for the first two years following their discharge from a sanatorium, and every six months thereafter. He feels that those with a history of contact should be X-rayed at once and every six months for a period of three years and annually thereafter.

Follow-Up, After-Care, Rehabilitation.—Next to finding the case of tuberculosis, adequate follow-up is of extreme importance,

276 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

particularly from the patient's standpoint. The patient should be referred to his private physician or to a clinic and the case reported to the local health department. Public health officials and local voluntary tuberculosis agencies are especially helpful in this follow-up stage. They can assist in arranging for sanatorial care and be of material assistance in checking on possible contacts in the home. If sanatoria are not available, outpatient supervision is far superior to no care at all.

In the development and the successful prosecution of a tuberculosis control program in any community, it is essential for public health officers to have the cooperation of the State and local medical society, management, labor, and voluntary agencies. This procedure will insure appropriate follow-up and after-care, and also pave the way for rehabilitation of the affected individual to industry. In this connection, from 65 to 75 per cent of the workers with minimal and moderately advanced tuberculosis¹⁹ can be expected to return to their former positions in industry after an adequate stay in a modern sanatorium. Many industrial organizations reemploy workers with arrested tuberculosis. Factors to be considered in the employment of a worker with arrested tuberculosis are as follows:¹⁷ (1) extent of the lesion, (2) completeness of the cure, (3) character of the job, and (4) the necessity for adequate medical supervision after return to work.

CONCLUSION

In this period of profound socio-economic stress every facility for searching out active cases and getting them under treatment should be employed to prevent an unfavorable effect on the present downward trend of the American tuberculosis mortality rate. The X-ray is a potent tool to this end and the medical departments of many industrial organizations have demonstrated how much can be done in promoting the control of tuberculosis. The plant physician should formulate a program making use of the X-ray for preemployment and periodic examinations of his employees. To provide for satisfactory disposition of cases found, the plant physician should also establish liaison with local workers in the field of tuberculosis control.

BIBLIOGRAPHY

1. Townsend, J. G.: Epidemiological Study of the Minor Respiratory Diseases by the Public Health Service (Preliminary and Progress Report). U. S. Pub. Health Rep., 39:2669 (October 24) 1924. Reprint No. 966.

2. Gover, Mary, Reed, L. J., and Collins, S. D.: Time Distribution of Common Colds and its Relation to Corresponding Weather Conditions. U. S. Pub. Health Rep., 49:811 (July 18) 1934. Reprint No. 1634.
3. Thomson, D., and Thomson, R.: The Common Cold. Annals of the Pickett-Thomson Research Laboratory. Vol. 8. Williams and Wilkins Company, Baltimore, 1932.
4. Paul, J. H., and Freese, H. L.: Study of Colds and Nasal Pharyngeal Flora in Spitzbergen. Am. Jour. Hyg., 17:517 (May) 1933.
5. Dochez, A. R.: Infections and Infestations: Respiratory Infections. In Preventive Medicine in Modern Practice. Hoeber, New York, 1942. P. 205.
6. Bartle, Harvey: Hygiene and Medical Care of Workers on American Railroads. In Industrial Hygiene, edited by A. J. Lanza and J. A. Goldberg. Oxford University Press, New York, 1939. P. 567.
7. Brown, J. W., Eaton, M. D., Meiklejohn, G., Lagen, J. B., and Kerr, W. J.: An Epidemic of Influenza. Results of Prophylactic Inoculation of a Complex Influenza A—Distemper Vaccine. Jour. Clin. Invest., 20:663 (November) 1941.
8. Horsfall, F. L., Jr.: The Present Status of the Influenza Problem. Jour. Am. Med. Assn., 120:284 (September 26) 1942.
9. Buchbinder, Leon: The Transmission of Certain Infections of Respiratory Origin. Jour. Am. Med. Assn., 118:718 (February 28) 1942.
10. Twort, C. C., Baker, A. H., Finn, S. R., and Powell, E. O.: The Disinfection of Closed Atmospheres with Germicidal Aerosols. Jour. Hyg. (London), 40:253 (May) 1940.
11. Williamson, A. E., and Gotaas, H. B.: Aerosol Sterilization of Air Borne Bacteria. Indust. Med., 11:40 (January) 1942.
12. American Public Health Association: The Control of Communicable Diseases. U. S. Pub. Health Rep., 50:1017 (August 9) 1935. Revision of 1940. Reprint No. 1697.
13. Chadwick, H. D., and Pope, A. S.: The Modern Attack on Tuberculosis. Commonwealth Fund, New York, 1942.
14. Improvement of Health in Twenty-Five Years. Current Comment. Jour. Am. Med. Assn., 119:267 (May 16) 1942.
15. Satisfactory Report on the Public Health. London Letter. Jour. Am. Med. Assn., 118:242 (January 17) 1942.
16. Sawyer, W. A.: Tuberculosis in Industry. Am. Rev. Tuberc., 39:456 (April) 1939.
17. Sawyer, W. A.: Control of Tuberculosis and Employment of the Tuberculous in Industry. Indust. Med., 10:221 (June) 1941.
18. Reid, Adachree: Control of Tuberculosis. III. Management of the Employee with Pulmonary Tuberculosis. Jour. Indust. Hyg., 23:35 (January) 1941.
19. Sherman, G. A.: Control of Tuberculosis in Industry. Indust. Med., 11:267 (June) 1942.
20. Hilleboe, H. E.: War Challenges Tuberculosis Control. Bull. Nat. Tuberc. Assn., 28:131 (September) 1942.
21. Sawyer, W. A.: Control of Tuberculosis. In Tuberculosis in Industry. Saranac Laboratory Symposium, 1941. National Tuberculosis Association, New York, 1942. P. 311.
22. Check List of Publications from the John J. Abel Fund for Research on the Common Cold to November, 1933 [The Johns Hopkins University]. Am. Jour. Hyg., 18:723 (November) 1933.

CHAPTER 20

ILLUMINATION, NOISE, AND RADIANT ENERGY

Allen D. Brandt, D.Sc., and Harry E. Seifert, C.E., M.S.P.H.

ILLUMINATION*

ON February 28, 1942, the Chairman of the War Production Board, announced that the President of the United States had officially launched a production drive with certain war production quotas which had to be met in that year. To meet the specified quotas each war production plant was asked to organize a Production Drive Committee to give close attention to such problems as: (1) taking care of tools, (2) preventing breakdowns, (3) cutting down accidents, (4) good lighting, (5) maintenance and repair, (6) adapting old machines to new uses, (7) cutting wastage, (8) breaking production bottlenecks, and (9) using every machine to the fullest extent.

From this list of nine items it will be recognized that the solution of the lighting problem will greatly contribute toward the solution of the others. In wartime good lighting might be classified as both an offensive and a defensive weapon. As an offensive weapon, it increases human efficiency and production by conserving priceless manhours. As a defensive weapon it minimizes eyestrain, reduces accidents and provides for human safety, and protects the manufactured products from the destructive effects of carelessness and sabotage.

BENEFICIAL EFFECTS OF GOOD ILLUMINATION

Illumination is a factor of primary importance which affects the environment in every industrial establishment. The beneficial effects of good illumination, both natural and artificial, have been established in extensive tests over many years. The advantages to industry are many: (1) greater accuracy of workmanship, resulting in an improved quality of product with less spoilage and rework, (2) increased production and decreased costs, (3) better utilization of floor space, (4) greater ease of seeing es-

* Based on information contained in material cited,¹³ with the permission of the Illuminating Engineering Society.

354 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

pecially among older employees, thus making them more efficient, (5) less eyestrain among employees, (6) improved morale among employees resulting in decreased labor turnover, (7) more easily maintained cleanliness and neatness in the plant, and (8) greater safety.

Greater Accuracy of Workmanship¹

Under good illumination it is possible to see an object of much smaller size than under poor illumination. Thus a closer check can be made throughout the manufacturing process which will result in earlier discovery of visible defects, permitting rejection prior to final inspection.

Increased Production

It takes time to see—the eye is somewhat like a camera in this respect. An increase in illumination from one footcandle to a moderate level of approximately 20 footcandles, a condition often occurring upon the installation of a modern lighting system, results in increasing the speed of seeing approximately three times.² This enormous improvement in perception and recognition of surroundings affects practically everything the worker does. It reduces the time required for seeing and some of this time, at least, becomes available for production. The experiences of many plants which have improved their lighting bear out this point.³

Better Utilization of Floor Space⁴

A uniform level of general lighting makes possible the most efficient arrangement of machinery and conveyors and better utilization of floor space. Manufacturers have discovered that more work can be achieved with less floor space when the work flows in straight lines through assembly or inspection sections. Good lighting facilitates such proper arrangement of the work and practically eliminates the likelihood for crowding.

Greater Ease of Seeing

Very frequently the older employee is well fitted physically and mentally for the responsible work for which his years of experience have prepared him. In many instances, however, failing vision will prevent such an employee from carrying on exacting work and thus he is relegated to simple routine tasks

in which his experience is of little value. It is desirable to preserve the experience of the older worker and receive the advantage of his long accumulated skill and knowledge.

It has long been known that as the eyes grow older there is a progressive loss in visual acuity and the prevalence of defective vision increases markedly. Much can be done to give assistance to eyes that are defective. Eyeglasses may correct refractive errors and permit the eyes to focus upon near and far objects. Higher illuminations are likewise an effective aid toward better seeing.

Many of these valuable, skilled, older workers can continue to perform efficiently if the simple expedient of assisting their eyes with good illumination is adopted.

Less Eyestrain

It should not be construed that good lighting is of assistance only to the older employees. Good lighting also aids all the visually handicapped to a greater extent than those with perfect vision, but even those in the latter group find, under good lighting, a noticeable improvement in eye comfort which results in reduced fatigue.

Improved Morale of the Employees

There is an important psychological effect connected with cheerful, pleasant, modern working surroundings as compared to the dim, gloomy interiors which were formerly so prevalent. In addition to the more cheerful appearance of a well-lighted interior, many minor frustrations due to poor lighting which continually harass the workers are eliminated; it is sufficient to refer to the difficulty in reading scales and micrometers, and to the finding of proper drills and other tools.

Plant Cleanliness

All industry has found that cleanliness invariably pays. Poor illumination makes it difficult to see into corners or under machinery and these dark areas inevitably collect dirt and waste which would otherwise be cleaned out. Where dirt can be seen it is more likely to be removed. In the well-lighted plant such dingy areas do not exist and sanitary conditions prevail.

In industrial plants that have their own engineering departments it is desirable that the combined efforts of the electrical engineering department, the operating department and the safety

356 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

department be enlisted to secure adequate maintenance of lighting equipment and to study lighting problems.

It is urged that those plants which do not have engineering departments consult a competent illuminating engineer.

Safety

Engineering for safe plant operation consists essentially of preparing a safe environment for the worker. The environment should be designed to match and to compensate for the limitations of human capability. On the other hand, the worker must understand his personal responsibilities regarding acts which might conceivably cause injury to himself or to others, and carefully follow plant safety regulations. The admirable activities of those organizations and individuals interested in the promotion of safety are successfully implanting this sense of responsibility in the individual worker.

However, as revealed by an analysis of accidents and their causes, this is but one phase of the safety problem. All personal injury accidents involve a combination of *personal* and *mechanical causes*. The chain of circumstances or series of causes which has brought a worker to the verge of an injury frequently can be broken only if the worker can see quickly and accurately the causes, and hence act to prevent the accident.

Any factor which aids seeing will increase the probability that the worker will detect the causes of an accident and act to avert it. It is realized that with rapidly-moving material, mechanical failures often result in accidents occurring too rapidly for any reaction on the part of the worker. However, mechanical failures of this nature are usually preceded by evidences of undue stresses or strains which may be detected if sufficient illumination is provided.

The close correlation between the personal injury rates and illumination is not generally understood. In most cases, where accidents are attributed to poor illumination, they occur because there is an improper quality of illumination or practically no illumination at all. Poor or indifferent lighting, even though it may provide measurable quantities of light, has been frequently overlooked as a contributing cause of accidents. Many factors associated with poor illumination, such as glare, light reflected from the work, and dark shadows, hamper seeing and cause after-images and excessive visual fatigue which are important contributing causes of industrial accidents. Many accidents are also

caused by delayed eye adaptation when coming from bright surroundings into dark interiors. Frequently accidents which are attributed to the worker's carelessness can actually be traced to difficulty of seeing.⁵

One important cause of industrial losses is the minor accident where the employee may or may not report for first aid but continues his work, with a decrease in the quantity and quality of his work.

The condition of the illumination at the point of accident and in the surrounding area should always be inspected and reported in accident investigations.

FACTORS OF GOOD ILLUMINATION

There are many factors involved in good illumination. Lighting installations, therefore, should be designed by a competent illuminating engineer. However, those who live with the lighting and those who must justify its cost should be acquainted with some of the factors to be considered. These can be summed up under the headings of *quality*, which includes, among other things, the color of light, its direction, diffusion, and absence of glare, and *quantity*, or the amount of illumination.

Quality of Lighting

The quality of the lighting⁶ whether natural or artificial is highly important in providing good seeing conditions. Glare, diffusion, direction, and distribution have significant effects on visibility and the ability to see easily, accurately and quickly.

Glare.—Glare may be defined as any brightness within the field of vision of such character as to cause discomfort, annoyance, interference with vision, or eye fatigue. It is one of the most common and serious faults of lighting installations.

Glare is objectionable because: (1) when continued it tends to injure the eye and disturb the nervous system; (2) it causes discomfort and fatigue and thus reduces the efficiency of the worker, and (3) it interferes with, and often prevents, clear vision and thus reduces efficiency, and in many instances increases the risk of accidents or injury to the workers. From both a humanitarian and a business viewpoint, the owner or operator of a factory should be interested in avoiding glare whether caused by daylight or by artificial light.

There are two common forms of glare, *direct* and *reflected*. *Direct glare* is caused by excessive brightness or brightness-con-

358 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

trast within the visual field, that is, unshielded lamps or high-brightness surfaces of fixtures.

To reduce direct glare from the artificial lighting, direct general-lighting luminaries should be mounted at a sufficient height to keep them well above the normal line of vision. They should be properly designed to limit both the brightness and the quantity of light emitted in directions directly below the horizontal since such light is well within the normal field of view and interferes with vision.

High brightness-contrasts should be avoided. For example, an unshielded lamp viewed against the low brightness of a dark ceiling may be very glaring, similarly, a bright window seen against darker surrounding walls.

Supplementary lighting sources should be carefully designed so that the light is confined to the immediate working area. Failure to observe this precaution may cause extreme annoyance not only to the worker using the source but to others in the vicinity. Care should also be exercised to prevent excessive brightness-contrasts between the work and the surroundings.

Reflected glare, as its name implies, is caused by high brightnesses, images or brightness-contrasts reflected from ceilings, walls, desk tops, or other surfaces within the visual field such as materials and machines. These brightnesses are accentuated when the surfaces are glossy or specular in character, such as highly-polished machine parts, smooth-finished surfaces, varnished table tops or other highly-reflective surfaces. Reflected glare is frequently more annoying than direct glare because it is so close to the line of vision that the eye cannot avoid it. The effect of reflected glare for a given image brightness is reduced with higher levels of general illumination due to the reduction in contrast.

*Diffusion and Distribution of Light.*⁶—Some directional and shadow effects are desirable in general illumination for accentuating the depth and form of solid objects, but harsh shadows should be avoided. Shadows are softer and less pronounced when diffusing units and units having a wide distribution of light are used, since then the object is illuminated from many sources. Alternate light and dark areas in strong contrast are undesirable because the eye has difficulty in adjusting itself to the two illuminations and seeing becomes tiring. For this reason, purely local lighting restricted to a small work area is unsatisfactory unless there is sufficient general illumination in the room.

Clearly defined shadows, without excessive contrast, are a distinct aid to sight in certain types of operations such as engraving on polished surfaces, scribed layout work, and textile inspection. When such shadow effect is indicated, it is best obtained by supplementary directional light combined with diffused illumination of ample intensity.

Much attention has been given to measurement of footcandles on the horizontal plane. Actually many of the seeing tasks in industry are on vertical or nearly vertical surfaces. Hence the amount and the distribution of light on vertical surfaces may be of great importance.

Color Quality of Light.—It appears that with equal footcandles of illumination, variations in color quality of light have little or no effect upon clearness and quickness of seeing.^{7, 8} A recent study has indicated that the same is true for fluorescent light.⁹ However, in certain industries color discrimination is highly important, and light sources which provide lighting that will enable the matching to be performed most accurately should be used. This again is a matter in which the illuminating engineer should be consulted.

Color of Surroundings.—Light-colored surfaces serve several purposes in the factory. They are of particular value in providing a high utilization of light because they reflect more light toward the working areas. Also, bright window areas and artificial light sources are less uncomfortable to the eye when viewed against light backgrounds.

Many progressive establishments are painting all of their machinery with light-tinted durable paints. This provides an increased amount of light which is reflected to the otherwise shadowed sections of the machine. Some manufacturers paint stationary and moving parts of machines different colors to aid seeing and thus prevent accidents.

Quantity of Light

The desirable quantity of light for any particular installation depends primarily upon the work which is being done. The degree of accuracy, the fineness of detail to be observed, the color and reflectivity of the work as well as of the immediate surroundings materially affect the distribution of brightness which will produce maximum seeing conditions. Investigations in the field and laboratory have proved that as the illumination on the task is increased, the ease, speed and accuracy with which the task can

860 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

be accomplished are increased. These tests have not yet established an upper limit but the harmful effects of low-foot-candle values are well known.²

It is possible to measure quantity of light quickly and with reasonable accuracy by the use of any of the various meters employing light-sensitive cells. These instruments are direct-reading and simple, but they should be calibrated at frequent intervals. It is highly important that the measurement be made at the point and in the plane in which the seeing task is performed, whether it be horizontal, vertical, or at some intermediate angle. If lighting is a combination of natural and artificial illumination, that part due to natural light should be measured separately from that due to the artificial light since in many instances at one hour of the day there is a great amount of natural light while at a different time it may fail entirely.

Brightness measurements hitherto difficult of accomplishment are now easily made with a Brightness Meter.

Recommended Minimum Standards of Illumination.—The majority of the recommended values of illumination in Table 1¹⁹ refers to the general lighting or lighting throughout the total area involved as measured on a horizontal plane 30 inches above the floor. In some instances where an illumination of more than 50 footcandles is necessary it may be obtained by a combination of general lighting plus supplementary lighting at the point of work. An asterisk after the footcandle figure denotes that the combination of general and supplementary illumination is desirable.

The Illuminating Engineering Society has been studying the illumination needs of specific industries in recent years. Wherever reports of these industries have been completed, the footcandles included in Table 1 are taken from the appropriate report. In other instances the values are based upon current good practice. These reports¹⁰⁻¹⁷ should be consulted for detailed lighting specifications for manufacturing processes.

Attention is called to the fact that the values given are minimum operating values; that is, they apply to measurements of the lighting system in use, not simply when the lamps and reflectors are new and clean—and in almost every instance higher values may be used with greater benefit.

To insure that a given illumination will be maintained even where conditions are favorable it is necessary to design the system to give initially at least 25 per cent more light than the re-

ILLUMINATION, NOISE, AND RADIANT ENERGY

361

TABLE 1.—MINIMUM FOOTCANDLES IN SERVICE.^a RECOMMENDED MINIMUM STANDARDS OF ILLUMINATION FOR INDUSTRIAL INTERIORS. (These Foot-candle Values Represent Order of Magnitude Rather than Exact Levels of Illumination.)

	Minimum Footcandles in Service Measured 30 inches above the Floor		Minimum Footcandles in Service Measured 30 inches above the Floor
ASSEMBLY:		stationary and gravity	
Rough.....	10	crystallizers.....	5
Medium.....	20	Mechanical furnaces, gen-	
Fine.....	B*	erators and stills, me-	
Extra fine.....	A*	chanical driers, evapo-	
AUTOMOBILE MANUFACTUR-		rators, filtration, me-	
ING:		chanical crystallizers,	
Assembly line.....	B*	bleaching.....	10
Frame assembly.....	20	Tanks for cooking, extrac-	
Body manufacturing—		tors, percolators, nitra-	
Parts.....	20	tors, electrolytic cells..	15
Assembly.....	20	CLAY PRODUCTS AND CE-	
Finishing and inspect-		MENTS:	
ing.....	A*	Grinding, filter presses,	
BAKERIES:		kiln rooms.....	5
Assembly line.....	20	Molding, pressing, clean-	
Folding, assembling, past-		ing and trimming.....	10
ing, etc.....	10	Enameling.....	15
Cutting, punching and		Color and glazing.....	20
stitching.....	20	CLEANING AND PRESSING	
Embossing.....	20	INDUSTRY:	
BREWERIES:		Checking and sorting....	20
Brew house.....	5	Dry and wet cleaning and	
Boiling, keg washing and		steaming.....	10
filling.....	10	Inspection and spotting..	A*
Bottling.....	20	Pressing—	
CANDY MAKING:		Machine.....	20
Box department.....	20	Hand.....	50
Chocolate department—		Receiving and shipping..	10
Husking, winnowing,		Repair and alteration....	50
fat extraction, crush-		CLOTH PRODUCTS:	
ing and refining, feed-		Cutting, inspecting, sew-	
ing.....	10	ing—	
Bean cleaning and sort-		Light goods.....	20
ing, dipping, packing,		Dark goods.....	A*
wrapping.....	20	Pressing, cloth treating	
Milling.....	30	(oilcloth, etc.)—	
Cream making—		Light goods.....	10
Mixing, cooking and		Dark goods.....	20
molding.....	20	COAL TIPPLES AND CLEAN-	
Gum drops and jellied		ING PLANTS:	
forms.....	20	Breaking, screening and	
Hand decorating.....	50	cleaning.....	10
Hard candy—		Picking.....	A*
Mixing, cooking and		CONSTRUCTION—INDOOR:	
molding.....	20	General.....	10
Die cutting and sorting		ELEVATORS—FREIGHT AND	
30		PASSENGER.....	10
Kiss making and wrap-		ENGRAVING.....	A*
ping.....	30	FORGE SHOPS AND WELDING	10
CANNING AND PRESERVING.	20	GARAGES—AUTOMOBILE:	
CHEMICAL WORKS:		Storage—live.....	10
Hand furnaces, boiling			
tanks, stationary driers,			

* See reference footnote at end of table.

ILLUMINATION, NOISE, AND RADIANT ENERGY

363

TABLE 1.—Continued

<i>Minimum Footcandles in Service Measured 30 inches above the Floor</i>		<i>Minimum Footcandles in Service Measured 30 inches above the Floor</i>	
Conference room—		POWER PLANTS, ENGINE	
General meetings.....	25	ROOM, BOILERS:..	
Office activities—See		Boilers, coal and ash	
deskwork		handling, storage bat-	
Corridors and stairways..	5	tery rooms.....	5
Deskwork—		Auxiliary equipment, oil	
Intermittent reading		switches and transform-	
and writing.....	25	ers.....	10
Prolonged close work,		Engines, generators, blow-	
computing, studying,		ers, compressors.....	20
designing, etc.....	50	Switchboards.....	30
Reading blueprints and		PRINTING INDUSTRIES:	
plans.....	30	Type foundries—	
Drafting—		Matrix making, dress-	
Prolonged close work,		ing type.....	A*
art drafting and de-		Font assembly—sort-	
signing in detail.....	50	ing.....	B*
Rough drawing and		Hand casting.....	30
sketching.....	30	Machine casting.....	20
Filing and index refer-		PRINTING PLANTS:	
ences.....	25	Presses.....	30
Lobby.....	10	Imposing stones.....	A* C*
Mail sorting.....	25	Proof reading.....	A*
Reception rooms.....	10	ELECTROTYPING:	
Stenographic work.....	50	Molding, finishing, level-	
Vault.....	10	ing molds, routing,	
PACKING AND BOXING.....	10	trimming.....	B*
PAINT MIXING.....	10	Blocking, tinning.....	30
PAINT SHOPS:		Electroplating, washing,	
Dipping, simple spraying,		backing.....	20
firing.....	10	PHOTO ENGRAVING:	
Rubbing, ordinary hand		Etching, staging.....	20
painting and finishing		Blocking.....	30
art, stencil and special		Routing, finishing, proof-	
spraying.....	20	ing.....	B*
Fine hand painting and		Tint laying.....	A*
finishing.....	B*	RECEIVING AND SHIPPING..	10
Extra fine hand painting		RUBBER TIRE AND TUBE	
and finishing (automob-		MANUFACTURING:	
ile bodies, piano cases,		Stock preparation—	
etc.).....	A*	Plasticating.....	20
PAPER BOX MANUFACTUR-		Milling.....	20
ING:		Calendering.....	30
Light.....	10	Branbury.....	20
Dark.....	20	Fabric Preparation—	
Storage.....	5	Stock Cutting.....	30
PAPER MANUFACTURING:		Bead Building.....	30
Beaters, grinding, calen-		Tube Tubing Machines..	20
dering.....	10	Tread Tubing Machines..	20
Finishing, cutting, trim-		Tire building—	
ming, paper making		Solid tire.....	20
machines.....	20	Pneumatic tire.....	50
PLATING.....	10	Curing department—	
POLISHING AND BURNISH-		Tube curing.....	B*
ING.....	20	Casing curing.....	B*

* See reference footnote at end of table.

364 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

TABLE 1.—Continued

<i>Minimum Footcandles in Service Measured 30 inches above the Floor</i>		<i>Minimum Footcandles in Service Measured 30 inches above the Floor</i>	
RUBBER TIRE AND TUBE MANUFACTURING:—Cont'd.		Storage, packing and ship- ping.....	
Final inspection—			10
Tube.....	B*	SHOE MANUFACTURING	
Casing.....	A*	(RUBBER):	
Wrapping.....	20	Washing, coating, mill run compounding.....	10
Warehouse.....	5	Varnishing, vulcanizing, calendering, upper and sole cutting.....	30
MECHANICAL RUBBER		Sole rolling, lining, mak- ing and finishing pro- cesses.....	50
GOODS:		SOAP MANUFACTURING:	
Stock preparation—		Kettle houses, cutting, soap chip and powder..	10
Plasticating.....	20	Stamping, wrapping and packing, filling and packing soap powder..	20
Milling.....	20	STAIRWAYS, PASSAGEWAYS.	
Calendering.....	30		5
Branbury.....	20	STONE CRUSHING AND	
Fabric preparation—		SCREENING:	
Stock cutting.....	30	Belt conveyor tubes, main line shafting spaces, chute rooms, inside of bins.....	5
Hose looms.....	30	Primary breaker room, auxiliary breakers un- der bins.....	5
Molded products.....	B*	Screens.....	10
Extruded products.....	30	STORAGE BATTERY MANU- FACTURING:	
Curing.....	B*	Molding of grids.....	10
Inspection.....	A*	STORE AND STOCK ROOMS:	
Boxing.....	20	Rough bulky material...	5
Warehouse.....	5	Medium or fine material requiring care.....	10
SHEET METAL WORKS:		STRUCTURAL STEEL FABRI- CATION.....	
Miscellaneous machines, ordinary bench work..	20		10
Punches, presses, shears, stamps, spinning, me- dium bench work...	20 C*	SUGAR GRADING.....	
Tin plate inspection...	B* C*		30
SHOE MANUFACTURING		TESTING:	
(LEATHER):		Rough.....	20
Cutting and stitching—		Fine.....	30
Cutting tables.....	20	Extra fine instruments, scales, etc.....	A*
Marking, buttonholing, skiving, sorting, vamping and counting—		TEXTILE MILLS (COTTON):	
Light materials.....	20	Opening, mixing, picking, carding and drawing...	10
Dark materials.....	50	Slubbing, roving, spinning	20
Stitching—		Spooling, warping on comb.....	20
Light materials.....	50	Beaming and slashing on comb—	
Dark materials.....	B*	Gray goods.....	20
Making and Finishing—		Denims.....	B*
Stitchers, nailers, sole layers, welt beaters and scarfers, trim- mers, welters, last- ers, edge setters, sluggers, randers, wheelers, treers, cleaning, spraying, buffing, polishing, embossing—			
Light materials.....	30		
Dark materials.....	50		

* See reference footnote at end of table.

TABLE 1.—Continued

Minimum Footcandles in Service Measured 30 inches above the Floor	Minimum Footcandles in Service Measured 30 inches above the Floor
Inspection— Gray goods (hand turn- ing)..... 50 Denims (rapidly mov- ing)..... A* Automatic tying-in, weav- ing..... B* Drawing-in by hand..... A* Weaving..... 25	WOOLEN: Carding, picking, wash- ing, combing..... 15 Twisting, dyeing..... 15 Drawing-in, warping.... A* Weaving— Light goods..... 25 Dark goods..... 50 Knitting machines..... 20
SILK AND RAYON MANU- FACTURING: Soaking, fugitive tinting, and conditioning or set- ting of twist..... 10 Winding, twisting, re- winding, and coning, quilling, slashing..... 30 Warping (silk or cotton system) on creel, on running ends, on reel, on beam, on warp at beaming..... 50 Drawing-in— On heddles..... A* On reed..... A* Weaving— On heddles and reeds.. 10 On warp back of har- ness..... 20 On woven cloth..... 30	TOBACCO PRODUCTS: Drying, stripping, general 10 Grading and sorting..... A* TOILETS AND WASH ROOMS 10 UPHOLSTERING—AUTOMO- BILE, COACH FURNITURE. 20 WAREHOUSE 5 WELDING 30 WOODWORKING: Rough sawing and bench work..... 15 Sizing, planing, rough sanding, medium ma- chine and bench work, glueing, veneering, coo- perage..... 20 Fine bench and machine work, fine sanding and finishing..... 50

* Lighting recommendations for the more difficult seeing tasks, as indicated by A, B, and C in the foregoing table, are given in the following:

GROUP A.—*These seeing tasks involve (a) the discrimination of extremely fine detail under conditions of (b) extremely poor contrast, (c) for long periods of time. To meet these requirements, illumination levels above 100 footcandles are recommended.*

To provide illumination of this order, a combination of at least 20 footcandles of general lighting plus specialized supplementary lighting is necessary. The design and installation of the combination systems must not only provide a sufficient amount of light but also must provide the proper direction of light, diffusion, eye protection, and insofar as possible must eliminate direct and reflected glare as well as objectionable shadows.

GROUP B.—*This group of visual tasks involves (a) the discrimination of fine detail under conditions of (b) a fair degree of contrast (c) for long periods of time. Illumination levels from 50 to 100 footcandles are required.*

To provide illumination of this order a combination of at least 20 footcandles of general lighting plus specialized supplementary lighting is necessary. The design and installation of the combination systems must not only provide a sufficient amount of light but also must provide the proper direction of light diffusion, eye protection, and insofar as possible must eliminate direct and reflected glare as well as objectionable shadows.

GROUP C.—*The seeing tasks of this group require the discrimination of fine detail by utilizing (a) the reflected image of a luminous area or (b) the transmitted light from a luminous area.*

The essential requirements are (1) that the luminous area shall be large enough to cover the surface which is being inspected and (2) that the brightness be within the limits necessary to obtain comfortable contrast conditions. This involves the use of sources of large area and relatively low brightness in which the source brightness is the principal factor rather than the footcandles produced at a given point.

366 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

quired minimum. In locations where the dirt will collect rapidly and where adequate maintenance is not provided, the initial value should be at least 50 per cent above the minimum requirement.

Where safety goggles are worn, the light reaching the eye is likely to be materially reduced and the general level of lighting should, therefore, be increased accordingly in such locations.

In addition to the foregoing table of recommended minimum standards, Table 2 presents the recommended minimum illumination for many of the war production activities not specifically included in Table 1.

NOISE

There is both practical and experimental evidence to indicate that noise produces fatigue, impaired hearing, neuroses, decreased efficiency, and emotional disturbances.¹⁹ Noise levels of 90 decibels (intensity of noise in an airplane) and higher have been found by experience to be harmful to the human ear.²⁰ Exposure to prolonged noise at lower levels, including the intensity of many occupational noises, is also harmful.²¹

As a guide in the evaluation of a noise problem, it is well to know that the intensity of noise near an airplane with motor running is about 95 decibels; in a New York subway it is about 80 decibels; in a large stenographic room it is about 70 decibels; and the intensity of sound in usual conversation varies from 35 to 70 decibels. Intensity alone is not the deciding factor, however. Of equal importance is the nature of the operation, and whether the noise is continuous or interrupted. For example, the average conversation of workers does not interfere with other workers in a machine shop but any conversation interferes with occupants of a library. Similarly a carpenter hammering and sawing does not affect the normal working of other nearby carpenters, but would reduce very much the efficiency in a room where stenographic work is being performed.

To reduce or eliminate the production loss resulting from noise, it is necessary in many industries to reduce the intensity of noise exposures as far as is feasible with good engineering practice. Noise may be prevented, or removed from the workers, by one or more of the following methods: (1) elimination of noise at its source, (2) isolation of noisy operations, (3) reduction of noise by sound insulation, and (4) the use of personal protective devices against noise.

ILLUMINATION, NOISE, AND RADIANT ENERGY 367

TABLE 2.—RECOMMENDED MINIMUM STANDARDS OF ILLUMINATION FOR WAR PRODUCTION AND ASSOCIATED ACTIVITIES. (The Footcandle Values are Average in Service and Represent Order of Magnitude Rather than Exact Levels.)

	Minimum Footcandles in Service		Minimum Footcandles in Service
AIRPLANE MANUFACTURING:		Mechanical furnaces, generators and stills, mechanical driers, evaporators, filtration, mechanical crystallizers	
Stock parts—		Tanks for cooking, extractors, percolators, nitro-	10
Production	50	tors	15
Inspection	A*		
Parts manufacturing—		PRECISION WAR EQUIPMENT:	
Welding, drilling, riveting and screw fastening	30	Assembly and adjustment of range finders, binoculars, periscopes, timing equipment, gun sights, electronic devices, torpedo mechanisms, etc.	A*
Spray booths	30		
Sheet aluminum layout and template work; shaping and smoothing of small parts for fuselage, wing sections, cowling, etc.	50	PROTECTIVE INDUSTRIAL LIGHTING:	
Sub-assembly—		General	0.2
Landing gear, fuselage, wind sections, cowling and other large units	30	Vulnerable areas	1
Final assembly—			
Placing of motors, propellers, wing sections and landing gear; mounting of guns and other large equipment	30	SHELL LOADING PLANTS:	
Inspection of assembled ship and its equipment	B*	Fuse and booster manufacturing	50
Machine tool repairs	A*	Inspecting, cleaning and spraying of shell forging	30
ARTILLERY MANUFACTURING:		Loading of shells, bombs, mines and depth charges—	
Forging and casting of gun barrels and mounts	10	Hand	B*
Machining and grinding of gun barrels, breeches, mounts and carriages	30	Automatic	30
Measuring and testing of parts; barrel boring; machining and assembly of range adjusters, and firing mechanisms	B*	Cleaning and inspection	30
General assembly	50	Assembly of shells, bombs, mines and depth charges	50
CONSTRUCTION—GENERAL:		Packing and boxing, storage	10
Excavation	2		
Exterior	5	SHIPYARDS:	
Indoor	10	General	5
EXPLOSIVES:		Ways and fabrication areas	10
Hand furnaces, boiling tanks, stationary driers, stationary and gravity crystallizers	5		
		TANK MANUFACTURING:	
		Assembly line	B*
		Frame assembly	20
		Body manufacturing—	
		Parts	20
		Assembly	20
		Finishing and inspecting	A*

* Same as for Table 1.

368 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY**Elimination of Noise at Its Source**

The causes of much of the noise in industry are faulty design of machinery, worn machine parts, improper machine mounting, improper location of machines, and carelessness in operating machinery. While it may be expensive in some cases to eliminate these sources of noise, it is frequently a profitable investment over a period of years. Silent operation may be accomplished by (1) replacing worn parts early, (2) using well balanced parts, (3) mounting machinery and guards so that they will not vibrate, (4) keeping moving parts well oiled, (5) having direct or belt drive in place of open gears, or using nonmetallic gears where gears are necessary, and (6) mounting machinery on appropriate bases. A good example of an operation wherein noise has been effectively reduced is that of pressure riveting or welding in place of pneumatic riveting.

Isolation of Noisy Operations

Noise-producing machinery frequently requires only one or two operators, but is so located that many workers are exposed to the noise. Operations of this type should be isolated in well-insulated enclosures so that only the operators are exposed to the noise. Likewise, noisy motors and gears can frequently be housed in sound insulating enclosures to reduce the workers' exposure. Those workers who must remain near the noise may be protected by means of suitable ear protectors or may even be isolated from the noise in well-insulated chambers or rooms which are adequately ventilated. An excellent example of noise prevention by this method is that of testing airplane motors in which the motor test rooms are so well insulated that little noise escapes from the enclosure.

Reduction of Noise by Sound Insulation

Where a large part of the noise in a room or building is caused by reflection of the noise back and forth between the walls, ceiling, objects, and floors, a great reduction can be accomplished conveniently by covering as much of the reflecting surface as possible with suitable sound absorbing materials. An example of this method is the application of sound absorbing materials to the ceiling, and sometimes the walls, of air-conditioned office spaces.

Personal Protective Devices

Where one of the preceding methods is not applicable, or adequate, or does not protect all of the workers, cotton plugs or some of the commercial ear protectors²² may be used to reduce the effect upon the exposed workers. Some of these protective devices reduce the intensity of severe noises appreciably; at the same time, however, they permit the hearing of conversation and thus do not create the safety hazard which would exist if conversation could not be heard.

RADIANT ENERGY

The most important exposure to radiant energy, and one which has been increased many-fold by the war effort, is that of ultraviolet, infra-red, and intense visible light radiation from electric welding arcs. In addition to this important health hazard, there are exposures to infra-red radiation in the heavy metal industries, to roentgen rays and radium emanation in the inspection and testing departments of many industries, to radium, thorium, and other radioactive materials in luminous dial painting and illuminating tube manufacture, to potential hazards from mercury vapor lamps, and to infra-red from drying lamps.

The important exposure, as indicated above, is to the harmful rays produced in welding operations. However, the methods and protective devices for controlling these exposures are so well known and so effective that only a brief summary is necessary. Table 3 gives the protection required for different welding operations.²³

To protect the workers in nearby areas, the welding operations should be shielded as much as possible by means of suitable permanent or portable shields placed about the operation. On the other hand, the welding operation should not be enclosed to such an extent that a serious health hazard to the welder is produced by the reduced ventilation. See *Welding*, Chapter 11.

For continuous exposures to infra-red radiation in the heavy metal processing industries, permanent shields and barriers, as well as protective goggles and helmets, will serve adequately. Spot cooling, if practicable, is helpful to keep such workers comfortable. See *Air Conditioning*, Chapter 21.

X-ray testing equipment used in the inspection of materials presents a potential exposure to radiant energy which is readily controllable. All X-ray equipment should be so shielded or en-

370 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

closed by lead that none of the roentgen rays will escape into the room. Where this control is not adequate, protective clothing may be used but it is better to shield the machine properly. Frequent inspections are necessary to guard against any leaks which may result in serious consequences.

The radiation emitted by radium employed in material inspection is more difficult to control than roentgen rays. While lead sheathing around the radium reduces the intensity of the rays somewhat, depending upon the thickness of the lead, it does not eliminate the hazard entirely unless the lead casing is too thick to be practicable. The method of preventing serious

TABLE 3.—PROTECTION REQUIRED FOR WELDING OPERATIONS

<i>Operation</i>	<i>Protection</i>
Production welding at a permanent location.....	Permanent shield with proper density light filter; helmet or hand shield with proper density light filter; or goggles with proper density lens.
Working in the vicinity of a welding operation.....	Goggles or spectacles with No. 3 or No. 4 shade lens.
Light gas cutting and welding, and light electric spot welding..	Goggles or spectacles with No. 5 shade lens.
Gas cutting, medium gas welding, arc welding up to 30 amps..	Helmet, shield or goggles with No. 6 shade filter glass.
Heavy gas welding, arc cutting, and welding between 30 and 75 amps.....	Helmet, shield or in some cases goggles with No. 8 shade filter glass.
Arc welding and cutting between 75 and 200 amps.....	Helmet or shield with No. 10 shade filter glass.
Arc welding and cutting between 200 and 400 amps.....	Helmet or shield with No. 12 shade filter glass.
Arc welding and cutting above 400 amps.....	Helmet or shield with No. 14 shade filter glass.

health effects in this instance is to use as little radium as possible, to enclose it in a lead container, and for the operator to remain as far away as possible from the source of energy. The desired combination of these three factors is given in a chart commonly known as the Failla Radium Protection Chart. This chart is presented in the reference cited,²⁴ where complete information on radium protection may be found.

The war effort and the manufacture of new types of lighting tubes have increased tremendously the number of workers exposed to radioactive materials. The control measures are similar to those given in the preceding paragraph for radium except that the amounts of radioactive materials handled are much less and the protective measures may be relaxed accordingly. Luminous

dial painting is covered in detail under *Luminous Dial Painting* in Chapter 11 and the information cited²⁵ is applicable to all exposures of this nature.

Mercury vapor lamps present potential exposures to ultra-violet radiation. The potential health hazard may be eliminated by employing a different type of illumination. Where this is not feasible, frequent inspection should be made to determine whether a hazard exists and if it does, the offending lights should be screened to prevent the ultraviolet rays from reaching the workers.

Infra-red radiation from drying lamps is usually limited to the drying enclosure and presents no significant health hazard as a rule, since no workers are inside the drying enclosure for any length of time.

BIBLIOGRAPHY

ILLUMINATION

1. Cobb, P. W., and Moss, F. K.: The Effect of Brightness on the Precision of Visually Controlled Operations. *Jour. Franklin Inst.*, 199: 507 (April) 1925.
2. Luckiesh, M., and Moss, F. K.: *The Science of Seeing*. D. Van Nostrand Co., New York, 1937.
3. Hess, D. P., and Harrison, W.: The Relation of Illumination to Production. *Trans. Illum. Eng. Soc.*, 18:787 (November) 1923.
4. Austin, W. K.: Operating Advantages of Controlled Conditions Plants. *Illum. Eng.*, 36:99 (January) 1941.
5. Simpson, R. E.: Accidental Lighting Costs. *Trans. Illum. Eng. Soc.*, 23: 633 (July) 1928.
6. Luckiesh, M., and Moss, F. K.: Quality of Lighting. *Trans. Illum. Eng. Soc.*, 30:531 (July) 1935.
7. Luckiesh, M., and Moss, F. K.: Seeing in Tungsten, Mercury and Sodium Lights. *Trans. Illum. Eng. Soc.*, 31:655 (July) 1936.
8. Woodside, C. S., and Reinhardt, H.: Comparison of the Light from High Intensity Mercury Vapor Lamps and Incandescent Filament Lamps for Visual Tasks. *Trans. Illum. Eng. Soc.*, 32:365 (April) 1937.
9. Luckiesh, M., and Moss, F. K.: Vision and Seeing Under Light from Fluorescent Lamps. *Illum. Eng.*, 37:81 (February) 1942.
10. Illuminating Engineering Society, Committee on Industrial and School Lighting: Progress Report on Lighting in the Printing Industry. *Trans. Illum. Eng. Soc.*, 31:277 (March) 1936.
11. Illuminating Engineering Society, Committee on Industrial and School Lighting: Report on Lighting in the Textile Industry—Grey Goods and Denim. *Trans. Illum. Eng. Soc.*, 32:247 (March) 1937.
12. Illuminating Engineering Society, Committee on Industrial and School Lighting: Report on Lighting in the Shoe Manufacturing Industry. *Trans. Illum. Eng. Soc.*, 32:289 (March) 1937.
13. Illuminating Engineering Society, Committee on Industrial and School Lighting: Report on Lighting in the Candy Manufacturing Industry. *Trans. Illum. Eng. Soc.*, 32:483 (May) 1937.

372 PREVENTION AND CONTROL OF DISEASE IN INDUSTRY

14. Illuminating Engineering Society, Committee on Industrial and School Lighting: Studies in Lighting of Intricate Production, Assembly and Inspection Processes. Trans. Illum. Eng. Soc., 32:1019 (December) 1937.
15. Illuminating Engineering Society, Committee on Industrial and School Lighting: Lighting for Silk and Rayon Throwing and Wide Goods Weaving. Trans. Illum. Eng. Soc., 33:17 (January) 1938.
16. Illuminating Engineering Society, Committee on Industrial and School Lighting: Lighting for the Machining of Small Metal Parts. Trans. Illum. Eng. Soc., 34:21 (January) 1939.
17. Illuminating Engineering Society, Committee on Industrial and School Lighting: Lighting of Power Presses. Trans. Illum. Eng. Soc., 34:153 (February) 1939.
18. American Recommended Practice of Industrial Lighting. ASA Code A-11-1942. Illuminating Engineering Society, New York, 1942.

NOISE

19. McCord, C. P., Teal, E. E., and Witheridge, W. H.: Noise and Its Effect on Human Beings. Jour. Am. Med. Assn., 110:1553 (May 7) 1938.
20. McKenzie, D.: Noise and Public Health. Jour. State Med., 42:542 (September) 1934.
21. State of New York Department of Labor, Bureau of Women in Industry: Effect of Noise on Hearing of Industrial Workers. Special Bulletin No. 166. New York, 1930.
22. Knudsen, V. O.: Freedom from Noise. Indust. Med., 8:14 (January) 1939.

RADIANT ENERGY

23. U. S. Department of Commerce, National Bureau of Standards: American Standard Safety Code for the Protection of Heads, Eyes, and Respiratory Organs. National Bureau of Standards Handbook H24. Government Printing Office, Washington, D. C., 1938.
24. U. S. Department of Commerce, National Bureau of Standards: Radium Protection. National Bureau of Standards Handbook H23. Government Printing Office, Washington, D. C., 1938.
25. U. S. Department of Commerce, National Bureau of Standards: Safe Handling of Radioactive Luminous Compound. National Bureau of Standards Handbook H27. Government Printing Office, Washington, D. C., 1941.

INDEX

NOTE: Page numbers of charts and figures are in *italic type*.

- ABRASIVE blasting, health hazards in, 213
 cleaning, health hazards in, 213
 dusts, in grinding, 232
 Absence, accounting for, by worker, 464
 leave of, 404
 Absenteeism, 420-466
 analysis of data as factor in control, 462
 control of, 459
 dental factors involved, 88
 disciplinary reasons for, 458
 general work situation and, 458
 in women, industrial injuries and, 413
 nonindustrial injuries and, 413
 occupational diseases and, 413
 personal reasons for, 414, 458
 investigation of absences, 463
 personal reasons causing, 414, 458
 control of, 462
 by appeal to patriotism and generosity of workers, 463
 by moral persuasion, 462
 by morale building, 463
 records, 459, 480, 481
 causes, duration, etc., 459
 minimum requirements, 459
 number of workers, by color, sex, and age, 459
 reliability of rates, 462
 role of nurse in decreasing, 78
 sickness, 420
 average daily percentage of workers disabled, 428
 causes of, 427, 428, 437, 438, 440, 443, 444, 446, 447, 448, 448, 449, 451, 452, 453, 454
 control of, 462
 days of disability contributed by disabilities of seven days or less, 439, 440
 disability rates, 421
 by broad cause and age groups from absences contributing *t* days or less, 446
 Absenteeism, sickness, disability rates, by broad cause groups for absences lasting one calendar day or more, 452, 453, 454
 disabling, related to various factors and indexes, 424
 duration of disability, 435
 frequency and distribution of, 424, 425, 426, 427
 and duration of, 441, 441, 442
 frequency rate, 421
 by broad cause and age groups for absence lasting *t* days or more, 443, 444
 by broad cause groups from absences lasting one calendar day or more, 449, 451
 in women and men, 412
 malingering and, 423
 miscellaneous factors in, 456
 nonrespiratory - nondigestive causes and age, 448, 448
 per cent of workers compensated, 456
 percentage distribution according to broad cause groups, of days disabled on specific days of disability after onset, 437, 438
 physical examination after, 52
 rates, 421
 causes of differences, 422
 comparability of, 422
 effects of age, 423, 425, 428, 429, 444, 446, 447, 448, 448, 456, 457
 of epidemics, 429
 and season, 430, 431
 of maximum benefit period, 423, 455
 of notification, certification and verification procedures, 423
 of occupation, 434
 of racial differences, 435
 of season, 429

- Absenteeism, sickness, rates:
 effects of sex, 425, 427, 435, 436, 437, 438, 439, 440
 of time-changes, 430, 443
 quarterly frequencies, 432, 433, 434
 of waiting time, 422, 423, 452
 factors yielded by sick benefit organizations, 422, 423
 frequency of factors affecting, 423
 types of, 421
 Absenteeism, sickness, severity rate, 421
 time lost as measure of health, 421
 Absenteeism, social and economic conditions as factor, 458
 summary and conclusions regarding, 464
 venereal diseases as cause, 281
 visiting nurse service and, 72
 women and, 412
 work not available as cause, 458
 Accidents, control, program of, role of nurse in, 71
 in small plants, 71
 frequency, temperature and, 373, 374
 illumination and, 356
 prevention program, duties of nurse in, 71
 recommendations on, 79
 Accrued liability, 137
 Acetone in tetryl crystallization, 253
 Achievement tests for women, 397
 Acid, nitric, tank filling, health hazards in, 215
 pickling, 247
 Acne, cutting oils and, 176
 differential diagnosis, 177
 vulgaris, cutting oil acne and, 177
 Acrolein, in heat treating, 233
 toxic limit of, 264
 Acrylonitrile, toxic limit of, 264
 Activity, temperature and, 373
 Aerosols, 271
 agents employed in, 271
 attributes necessary for use in occupied rooms, 271
 Age as factor in sickness absenteeism, 423, 425, 428, 429, 443, 444, 446, 447, 448, 449, 456, 457
 Agricultural workers, exclusion of, from compensation benefits (with exceptions), 137
 Ague, brass foundry, 145
 Air, clean, equation for, 206
 collector, 204
 conditioning, 378-381
 comfort, 380
 control of dermatitis by, 381
 efficiency and, 378
 product control by, 379
 respiratory illness and, 380
 contaminants, mechanical ventilation and, 378
 contamination, control, 198-266
 control, by dilution ventilation, 206
 equipment for, maintenance, 211
 general considerations, 199
 isolation in, 207
 machinery placement and, 207
 minimum air velocities, table, 201
 substitution in, 207
 efficiency and, 198
 housekeeping and, 205
 water control of, 205
 duct, construction of, 203
 size of, 203
 exhauster, 204
 recirculation of, 204
 ultraviolet radiation of, in control of acute respiratory infections, 270
 velocity, 200
 contaminant removal and, 201
 hood and, equations, 202
 in ducts, 203
 plant layout and, 201
 Air-borne hypothesis in acute respiratory infections, 270
 Airplane hangars, minimum illumination for, 362
 manufacture, dermatitis in, 194
 minimum illumination for, 367
 motor cleaning, health hazards of, 215
 Alabama, U.S.P.H.S. District including, 14
 Alaska, U.S.P.H.S. District including, 14
 Albuminuria, rejection rate due to, 384
 selective placement policy and, 390
 Alcohol, butyl, toxic limit of, 264
 in lens cleaning, 236
 methyl, in tracer bullet charging, 260

- Alcohol, methyl, in type cleaning, 248
toxic limit of, 264
polyvinyl, as dermatitis preventive, 168
vapors, in colloid, 224
Alcoholic beverages, use of, and fatigue, 322
Alimentary type of lead poisoning, 142, 144
Alkali cleaning, health hazards in, 215
Allergy, industrial dermatitis and, 164
Alpha rays in radium, harmful effects, 149
Aluminizing, health hazards in, 216
Aluminum alloy finishing; health hazards in, 216
finishing, health hazards in, 216
Amatol break-up, health hazard in, 216
bucket cleaning, health hazard in, 216
cooling, health hazards of, 217
manufacture, dermatitis of, 193
pouring, health hazards in, 217
preparation, health hazards in, 217
puddling, health hazards in, 217
Ambulance drivers, 34
service, organization of, in emergency medical services, 102
Ambulances, requirements of plant for, 22
American College of Surgeons, costs of medical program, 27
interest in industrial hygiene, 123
qualifications of industrial physician, 30
standards for industrial medical service, 41
American Dental Association, Council on Dental Health, dental services and, 90
American Foundrymen's Association, industrial health activities of, 123
American Heart Association, public health education, 41
American Medical Association, Council on Industrial Health, 123
war program of, 126, 128
written standing orders, for industrial nurse, suggestions on, 78
American Public Health Association, affiliation with, 41
hygiene and sanitation in control of respiratory diseases, pamphlet, 271
American Red Cross Home Nursing classes, nurse and, recommendations on, 82
nutritional education, 124
American Social Hygiene Association, interest in industrial hygiene, 123
American Society of Heating and Ventilating Engineers, interest in industrial hygiene, 123
American Standards Association, interest in industrial hygiene, 123
Amino acids, requirements, 327
Ammonia, oxidation, health hazards in, 218
toxic limit of, 264
Ammonium nitrate, dermatitis from, 162, 187, 193
dust, in amatol preparation, 217
Ammonium picrate, and physical examination, frequency of, 51
Amputations, selective placement policy and, 390
Amyl acetate, toxic limit of, 264
Anemia in benzene poisoning, 155
in lead poisoning, 143
in radium poisoning, 149
Aniline, distillation of, health hazards in, 218
manufacture of, health hazards in, 219
toxic limit of, 264
Ankyloses, selective placement policy and, 390
Anodizing, health hazards of, 229
Anopheles, community sanitation and, 343
Anthraxis, 151
Anthrax, 151
Antimony in brush painting, 244
in spray painting, 245
Applicants, munitions plants rejection rates, 384
Aprons, dermatitis prevention and, 169
Aptitude tests for women, 397
Arc, welding, radiant energy in, 369
Architect, need for, in constructing plant infirmary, 13
Arizona, U.S.P.H.S. District including, 15

- Arkansas, U.S.P.H.S. District including, 15
 Arsenic, in electroplating, 230
 water pollution from, 338
 Arsine, in electroplating, 230
 in pickling, 247
 toxic limit of, 264
 Arterial hypertension, and employment, 45, 60
 Arthritis, selective placement policy and, 391
 Artificial respiration in carbon monoxide poisoning, 156
 Artillery manufacturing, minimum illumination for, 367
 Asbestosis, 151
 bodies, 154
 diagnosis, 153
 Ascorbic acid, recommended daily allowance, 329
 Asphalt paint dermatitis, 193
 Assembly operations, minimum illumination for, 361
 Association of Industrial Physicians and Surgeons, affiliation with, 41
 Athlete's foot, dermatitis and, 195
 treatment, 195
 Atmospheric contamination, 338
 control of, 198-266
 industry and, 337
 plant sanitation and, 345
 Automobile manufacturing, minimum illumination for, 361

 BAKERIES, community sanitation and, 342
 minimum illumination for, 361
 Ballistics testing, health hazards of, 219
 Balloon manufacture, health hazards in, 221
 Barium peroxide, in igniter mixture preparation, 234
 in tracer bullet charging, 260
 toxic limit of, 264
 Beds, in plant infirmary, 20
 restroom specifications, 350
 Benefits, sickness, amounts allowed, 136
 effect of, on absenteeism rates, 422, 424
 financing, 136
 maximum periods, effect on absenteeism rates, 422, 455
 per cent of workers participating in, 456
 Benefits, sickness, waiting period, effect on absenteeism rate, 422, 452
 Benzene, and physical examination, frequency of, 51
 as health hazard, 7
 in brush painting, 244
 in rubber goods fabrication, 249
 in tetryl crystallization, 253
 in type cleaning, 248
 nitration, health hazards in, 221
 poisoning, 154
 blood picture in, 155
 chronic, 155
 medical control measures, 155
 pathologic changes, 155
 symptoms, 155
 urine in, 155
 toxic limit of, 264
 vapors, in benzene nitration, 221
 Benzine, 155
 Benzol. See *Benzene*.
 Beri-beri, 329
 Beta rays in radium, harmful effects, 149
 Black powder, 188
 Blacked-out building, mechanical ventilation in, 377
 Blanket compensation laws, 135
 Blasting, abrasive, health hazards in, 213
 Blindness, selective placement policy and, 390
 Blood, lead content, normal and abnormal, 143
 picture, in benzene poisoning, 155
 in lead poisoning, 143
 tests, for syphilis, injustices from, 281, 282
 Blue lip, 192
 Boat manufacture, rubber, health hazards in, 249
 Body odor, mechanical ventilation and, 377
 ventilation rate and, 376
 Boilers, minimum illumination for, 363
 Boils, cutting oils and, 176
 differential diagnosis, 177
 TNT, 192
 Bomb loading, dermatitis and, 191
 Bone marrow, changes in, in benzene poisoning, 154
 Bones, decalcification of, in calcium inadequacy, 327
 lesions of, in radium poisoning, 149, 150

- Book binding, minimum illumination for, 361
 Booster cavity drilling, health hazards in, 222
 cup loading, health hazards in, 222
 tube loading, health hazards in, 222
 Boron, water pollution from, 338
 Boxing, minimum illumination for, 363
 Branch establishments, relation to home medical department, 26
 Brass chills, 145
 founders' ague, 145. See also *Lead poisoning*.
 poisoning, 191
 Bread, enriched, 332
 Breweries, minimum illumination for, 361
 Brombenzylcyanide dermatitis, 188
 Bullet casting, health hazards in, 234
 Burnishing, minimum illumination for, 363
 Burns, dermatitis and, 163
 in mustard gas manufacture, 189
 lewisite, treatment, 190
 Butyl acetate, toxic limit of, 264
 Butyl alcohol, toxic limit of, 264

 CADMIUM, in electroplating, 230
 industrial uses of, 146
 poisoning, 146
 differential diagnosis, 146
 symptoms, 146
 treatment, 147
 toxic limit of, 264
 Cafeterias, management-owned, 333
 need for, in industrial plants, 8
 nutritional education and, 331
 plant, nutrition and, 330
 responsibility of medical department in, 37
 womanpower and, 399
 Calcium, milk as source of, 327
 recommended daily allowance, 329
 requirements, dietary, 327
 California, joint interdepartmental action in industrial hygiene field, 118
 U.S.P.H.S. District including, 14
 Calories, recommended daily allowance, 329
 requirement, 326
 Camouflage paint manufacture, health hazards in, 223

 Cancer, as cause of absenteeism, 443
 selective placement policy and, 391
 Candy making, minimum illumination for, 361
 Canning, minimum illumination for, 361
 Cap for women in industry, 411
 Carbide tool manufacture, health hazards in, 223
 Carbon dioxide, toxic limit of, 264
 Carbon disulfide, in rubber goods fabrication, 249
 toxic limit of, 264
 Carbon filter in blacked-out building ventilation, 377
 Carbon monoxide, in ballistics testing, 219
 in forging, 231
 in heat treating, 233
 in motor testing, 241
 poisoning, 156
 symptoms, 156
 treatment, 156
 toxic limit of, 264
 Carbon tetrachloride, in incendiary mixture preparation, 234
 in leather cleaning, 236
 in rubber goods fabrication, 249
 in tracer bullet charging, 260
 in tracer mixture screening and mixing, 261
 in type cleaning, 248
 toxic limit of, 264
 vapors, in degreasing, 226
 Caries, vitamin deficiency and, 329
 Cartridge loading, protection in, 193
 manufacture, dermatitis from, 190
 Casual workers, exclusion of, in compensation laws, 137
 Casualty station, organization of, in emergency medical services, 100
 Cavity drilling, booster, health hazards of, 222
 Cellophane, as dermatitis preventive, 168
 Cement manufacturing, minimum illumination for, 361
 solvents, in balloon manufacture, 221
 Certification, method of, as factor in sickness absenteeism rates, 423
 Cheilitis, vitamin deficiency and, 329
 Chemical functions of State industrial hygiene units, 113
 sprays, in control of acute respiratory infections, 271

- Chemical works, minimum illumination for, 361
- Chemicals, war, dermatitis caused by, 188
- Chest, disability diseases of, rejection rate due to, 384
 - x-ray examination, administrative procedures, 274
 - frequency of, in siliceous dusty trades, 275
 - in workers with evidence of tuberculosis, 275
 - in control of chronic respiratory infections, 273
 - methods, 274
- Children, care of, womanpower and, 416
- Children's Bureau, U. S. Department of Labor, 40, 108
 - nutritional education and, 333
 - statement on pregnancy, 405
- Chills, brass, 145
 - oxide, 145
- Chloracetophenone dermatitis, 188
- Chloracne, prevention of, 177
- Chlorine requirements, dietary, 327
- Chloro compounds, skin sensitization by, 162
- Chlorovinyl-dichlorarsine, 190
- Chromates, water pollution from, 338
- Chromic acid, mists, in electroplating, 229
 - toxic limit of, 264
- Civilian defense organizations, relationship of plant medical department to, 40
- Clay products, minimum illumination for, 361
- Cleaning, abrasive, health hazards in, 213
 - minimum illumination for, 361
- Cleanliness, community, 335
 - dermatitis and, 168
 - plant, illumination and, 355
 - sanitation and, 351
- Clinic assistants, nonprofessional, 33
- Closets, chemical, specifications, 348
- Cloth products, minimum illumination for work with, 361
- Clothing, dermatitis and, 162, 168
 - in mustard gas manufacture, 189
 - protective, for women, 410
 - women in industry and, 409
- Coal cleaning plants, minimum illumination for, 361
- Coal tipples, minimum illumination for, 361
- Coal-oil in lens cleaning, 236
- Coal-tar products, protective ointment against, 172
- Cold tinning process, health hazards of, 224
- Colds, epidemiology, 267
 - etiologic factors, 268
 - general control measures, 271
 - isolation in, 272
 - prevalence of, 268
 - prophylactic immunization with vaccines, 269
- Colic, lead, 142
- Collector, air, 204
- Colloiding, health hazards of, 224
- Colorado, U.S.P.H.S. District including, 15
- Comedones, cutting oils and, 176
- Committee on Healthful Working Conditions, National Association of Manufacturers, 123
 - survey, 385
- Common cold. See *Colds*.
- Communicable diseases, acute, reporting to health authorities, 38, 39
 - control of, 336
- Communities Facilities Act, 2
- Community Chest, medical director and, 41
- Community environment, wartime problems, 1
 - facilities, wartime disruption of, 3
 - hospital and health facilities, appraisal of, before construction of war plant, 14
 - importance of industrial hygiene to, 106
 - relationships, women in industry and, 414
- Compensation, benefits, amounts allowed, 136
 - effects of, on absenteeism rate, 422, 424
 - financing, 136
 - maximum periods, effect on absenteeism rate, 422, 425
 - per cent of workers participating in, 456
 - waiting period, effect on absenteeism rates, 422, 452
- cases, assistance of public health administrators in, 121

- Compensation costs, of different types of occupational diseases, comparison of, 131
for occupational disease, States with laws for, 133
insurance, 136
laws, accrued liability, 137
comparison of schedule and general coverage, 135
compulsory, 137
coverage of agricultural and domestic workers, 137
definitive general coverage, 135
elective, 137
exclusion of agricultural and domestic workers (with exceptions), 137
of casual workers, 137
of small employers, 137
general or blanket coverage, 135
States having, 135
limited disability clauses, 138
limiting provisions, 137
maximum periods, effect on absenteeism rates, 422-455
medical benefits, 136
service, time limits of, 136
monetary benefits, 136
penalty provisions, 137
provisions of, 135
handicapped workers, 138
schedule or limited coverage, 135
second-injury provisions, 138
States with, 138
silicosis coverage, 152
States having, 135
States having, 133
types of, 135
waiting period, 136
effect on absenteeism rate, 422, 452
waiver clauses, 138
sickness, effect of maximum period on absenteeism rate, 452, 455
effect of waiting period on absenteeism rate, 422, 452
per cent of workers participating in, 456
Concentration, hunger and, 326
Conditioning air. See *Air-conditioning*.
Conference on Day Care of Children of Working Mothers, 416
Conjunctivitis, mercury fulminate and, 187
Connecticut, activities of medical profession in furthering war-time program of industrial hygiene, 128
U.S.P.H.S. District including, 14
Construction, general, minimum illumination for, 367
indoor, minimum illumination for, 361
Consultants, part-time, in plant medical department, 29
standards for, in plant medical department, 31
Contaminants, air, control of, 198-266
definition, 198
Control of occupational diseases, 131-382
Control point of plant infirmary, 18
Cooling season, mechanical ventilation in, 377. See also *Air conditioning*.
Cooling, spot, in infra-red exposure, 369
Coroner's office, relationship of plant medical department to, 38
Coryza. See *Colds*.
Costs of plant medical department, 27
Cotton drying, health hazards of, 225
picking, health hazards of, 225
weighing, health hazards of, 225
Council on Dental Health, American Dental Association, dental services and, 90
Council on Industrial Health, American Medical Association, 123
medical supervision of workers, 10
war program of, 126, 128
written standing orders, for industrial nurse, suggestions on, 78
Counsellors, employees', 37
industrial nurses as, 70, 73, 78, 79
Coverage laws, types of, 135
Coveralls, dermatitis prevention and, 169
Crack testing, mercury, health hazards of, 239
Cream, vanishing, formula, 170
Crowding, in war areas, 2
ventilation rate and, 377

- Cup loading, booster, health hazards of, 222
- Cuspidors, plant sanitation and, 351
- Cutting oils, as health hazards, 7
dermatitis and, 175
treatment, 178
in machining, 239
- Cyanides, in electroplating, 229
in heat treating, 233
- Cyanosis, TNT, 192
- Cysts, cutting oils and, 176
- DEAFNESS, selective placement policy and, 390
- Decalcification therapy in radium poisoning, 150
- Decarbonizing, health hazards of, 226
- Defatting of skin, petroleum oils and, 176
- Defect, dynamic, rehabilitation and, 385
static, rehabilitation and, 385
stationary, rehabilitation and, 385
- Defense Health and Welfare Services, Federal Security Agency, 40
- Definition of industrial disease, 134
- Definitive general coverage laws, 135
- Degreasers, dermatitis from, 175, 179, 181
prevention, 180
- Degreasing, health hazards of, 226
ventilation formula for, 227
- Delaware, U.S.P.H.S. District including, 14
- Dental assistant, role of, in dental program, 92
factors, in occupational hazards, 89, 90
hygiene division, State department of health, dental services and, 90
hygienist, role of, in dental program, 92
infection in radium poisoning, 149
office, location of, 92
Practice Acts of States, dental services and, 91
program, dental prophylaxis, recommendations on, 95
education in, 95
emergency service, 95
examination service, 94
in small plants, 95
personnel, 93
physical equipment, 93
records required, 94
- Dental program, supplies for, 93
services, 88-97
consultative, 90
dental assistant and, 92
dental hygienist and, 92
dentist, relation to employee unit, 91
in large plants, 91
in small plants, 91
organization of, 96
need of, 88
in special industries, 90
on full-time basis, 91
on part-time basis, 91
problems involved, 88
program of, 89, 93. See also *Dental program*.
relation to medical and nursing services, 90
responsibility for cost of, by whom borne, 92
- Dentistry, 88-97
- Dentists, availability of, 92
full-time, 91
part-time, 91
plant, 32, 91
relation to employee unit, 91
- Departmental authority in relation to plant medical department, 25
- Depression, vitamin deficiency and, 329
- Dermatitis, 161-197
ammonium nitrate, 187, 193
asphalt paint, 193
athlete's foot and, 195
black powder, 188
brombenzylcyanide, 188
cartridge manufacture and, 190
chloracetophenone, 188
control by air conditioning, 381
cutting oil, 175
prevention of, 177, 178
skin type and, 176
treatment, 178
degreasers and, 175, 179, 181
diagnosis, 161
differential, 163
eruption, site of, 162
examination of patient in, 162
exposure and lesions, relation of, 162
lesions as aid in, 161
patch test in, 165
DNT, 187, 192
dopes and, 179, 180
electroplating and, 181

INDEX

475

- Dermatitis, ethyldichlorarsine, 190
 from fabric coating, 231
 history of, 161
 industrial, dermatophytosis and, 195
 kerosene, 193
 lead azide, 187, 193
 lewisite, 190
 mercury fulminate, 148, 186, 193
 metal preservatives and, 181
 mustard gas, 189
 oakite, 193
 occupational, diagnosis of, 161
 examination for, role of nurse in, 51
 in preplacement examination, 57
 ointment and, 169
 paint thinners and, 179, 180
 petroleum spirits causing, 193
 prevention, 167
 cleanliness and, 168
 clothing and, 168
 education in, 197
 ointment formulas, 170-172
 rust preventives and, 181
 seborrhoeic, occupational dermatitis and, 163
 smokeless powder, 188
 solvents causing, 175, 193
 specific irritants and, 175
 Stoddard solvent, 193
 tetryl, 182, 184, 191
 prevention, 183, 192
 treatment, 184
 TNT, 192
 dust and, 185
 prevention, 192
 treatment, 174
 war gas, 188
 welding and, 182
 worker selection and, 196
 Dermatophytosis, dermatitis and, 195
 Dermatoses Investigations Section, Division of Industrial Hygiene, National Institute of Health, 110
 Dermatoses, occupational, 64, 161-197. See also *Dermatitis*.
 Detonator, manufacture of, dermatitis in, 186, 187
 Development of industrial hygiene in United States, 107
 Dexterity tests for women, 397
 Diabetes mellitus, and employment, 44
 Diabetes mellitus, selective placement policy and, 391
 Dial painting, luminous, health hazards of, 237
 Dichlorethyl sulfide, 189
 Dichlorobenzene, toxic limit of, 264
 Diet as factor in fatigue, 310, 318, 321
 in industry, 325
 Dietitian, nutritional education and, 331
 Digestive diseases as cause of absenteeism, 427, 428, 433, 438, 439, 440, 444, 445, 447, 453, 454.
 Dilution ventilation, 206
 Dimethylaniline, 228
 sulfate, 228
 toxic limit of, 264
 Dinitrotoluene. See DNT.
 Diphenylamine, 229
 Diphenyls, dermatitis caused by, 163
 Disability rates in sickness absenteeism, 421
 by broad cause and age groups from absences contributing 1 day or less, 446, 447
 by broad cause groups from absences lasting one calendar day or more, 452, 454
 Disciplinary reasons for absenteeism, 458
 Diseases, causing absenteeism, frequency and distribution of, 427, 428, 433, 437, 438, 440, 443, 444, 446, 447, 448, 448, 449, 451, 452, 453, 454
 contagious, control of, 336
 reporting of, 38, 39
 in industry. See *Occupational diseases*.
 nonoccupational, dental factors and, 89
 plant medical services and, 64
 prevention of, by health program, 43, 297
 Dispensary plant, physical set-up, as factor in health education, 298
 District of Columbia, U.S.P.H.S. District including, 14
 DMA sulfation, health hazards of, 228
 DMAS nitration, health hazards of, 241
 DNT, 45
 and physical examination, frequency of, 51

- DNT, crushing, health hazards of, 228
 dermatitis, 187, 192
 dust, in sweetie barrel operation, 252
 in toluene nitration, 260
 screening, health hazards of, 228
 toxic limit of, 264
 Domestic workers, exclusion of, from compensation benefits (with exceptions), 137
 Doses, dermatitis from, 179, 180
 prevention, 180, 194
 Dowicide F in camouflage paint manufacture, 223
 DPA crystallization, health hazards of, 229
 packing, health hazards of, 229
 Dress, appropriate, for women in industry, 410
 Dressing rooms, specifications, 350
 Drinking cups, plant sanitation and, 346
 establishments, community sanitation and, 342
 fountains, plant sanitation and, 346
 Drop hammer operators, dermatitis prevention in, 194
 Drug eruptions, occupational dermatitis and, 163
 Duct, air, construction of, 203
 size of, 203
 velocity in, 203
 Dural poisoning, 194
 Dust, affections of lungs, 150. See also *Silicosis*.
 control, in sandblasting, 213
 definition, 198
 diseases caused by, 139
 hazards, new, in industry, 7
 metallic, in shotblasting, 214
 silica in sandblasting, 213
 in shotblasting, 214
 Dusty trades, frequency of periodic X-ray in, 275
 periodic examinations in, 154
 Dysentery, examination for, in food handlers, 54
 EAR protector, noise and, 369
 Eating establishments. See also *Cafeterias*.
 community sanitation and, 342
 minimum window requirement for, 376
 Economic factors in absenteeism, 458
 Eczema, allergic, cutting oils causing, 177
 differential diagnosis, 177
 inhibitors causing, 176
 industrial dermatitis and, 164
 Education, dermatitis prevention and, 197
 health, 297-307. See also *Health education*.
 plant sanitation and, 345
 program of, in venereal disease control, 285
 public health, 336
 role in nutrition, 331
 worker, in plant housekeeping, 212
 Efficiency, air conditioning and, 378
 air contamination and, 198
 glare and, 357
 hours of work and, 402
 noise and, 366
 Ejector, air exhaust by, 204
 Electric welding as health hazard, 6
 Electroplating, dermatitis and, 181
 health hazards of, 229
 Electrotyping, minimum illumination for, 363
 Elevators, minimum illumination for, 361
 Emergency treatment, opportunities for health education at, 297
 Emotional complications of injury and illness, 295
 conflicts at home, and fatigue, 322
 disturbance, noise and, 366
 Employees, capacity of, determination by preplacement examination, 44
 conferences with industrial physician, in venereal disease program, 288
 counsellors and, 37
 industrial nurses as, 70, 73, 78, 79
 key, physical examination of, frequency of, 51
 medical records, confidential nature of, 286
 objectives of venereal disease program, 283
 pool of, prospective, and physical examination, 46
 training of, in health matters, 301
 in job, 320
 transient, physical examination of, 48

INDEX

477

- Employees, venereal disease tests, 281, 282
 women. See *Women in industry*.
 Employment of handicapped persons. See *Handicapped workers*.
 of venereally infected persons, 282, 284, 287, 288
 of women. See *Women, employment of*.
 Encephalopathy, lead, 143
 differential diagnosis, 144
 Enclosures, ventilation by, 200
 Energy, radiant, 369-371
 Energy requirements, 325
 Engine room, minimum illumination for, 363
 Engineering functions of State industrial hygiene divisions, 113
 of jobs for maximum efficiency, 320
 Engineering Unit, Division of Industrial Hygiene, National Institute of Health, 110
 Engraving, minimum illumination for, 361
 Enteric disease in food handlers, examination for, 54
 Environment, community, and the war worker, 1
 sanitation and, 335
 working, problems of, 6
 Environmental control of respiratory diseases, 270
 factors in fatigue, 319
 hygiene, possible services by health, department in, 114
 Epidemics, effects of, on sickness absenteeism rates, 429
 in relation to season, 430, 431
 Epilepsy in preplacement examinations, 57
 Erethism, mercurial, 148
 Eruption, site of, in occupational dermatitis, 162
 Erythema multiforme, occupational dermatitis and, 163
 Erythrocytes, stippling of, in lead poisoning, 143
 Ether vapors in colloidizing, 224
 Ethyldichlorarsine dermatitis, 190
 Ethylene dichloride, in leather cleaning, 236
 in protectoscope manufacture, 249
 in rubber goods fabrication, 249
 Ethylene dichloride, toxic limit of, 264
 vapors, in degreasing, 226
 Examinations. See *Physical examination*.
 Examining rooms of plant infirmary, 21
 Exhauster, air, 204
 Expecterating, plant sanitation and, 351
 Explosive manufacture, health hazards of, 379
 Explosives, minimum illumination for, 367
 water pollution from, 338
 Eye, adaptation, accidents and, 357
 coordination tests for women, 397
 examination of, 61
 examining room, in plant infirmary, 20
 treatment room, in plant infirmary, 20
 Eyestrain, illumination and, 355
 FABRIC coating, health hazards of, 230
 Facilities, organization and operation of, 1-130
 Factory. See *Plant*.
 Failla radium protection chart, 370
 Family physician, role of, in combating fatigue, 323
 Fan, air exhaust by, 204
 Fatigue, 308-324
 adequate sleep and, 322
 as health hazard in industry, 7
 causes of, 309
 at work, 309
 off the job, 310
 chronic, disabling, 310
 combating, at work, 320
 off the job, 321
 role of industrial and family physicians in, 322
 community facilities and, 321
 definition of, 309
 emotional conflict at home and, 322
 environmental factors in, 319
 excessive, repeated, 310
 facilities for reducing, 399
 glare and, 357
 health education and, 321
 hours of work and, 315
 housing facilities and, 321
 in truck drivers, recent study, 311

- Fatigue, in truck drivers, recent study, results, 312
tests employed, 311
individual human factor in, 314
industrial causes and control, 308-324
job engineering and, 320
job placement and, 320
job training and, 320
meal frequency and, 326
measurement of, 310
altered functions a basis, 311
productive capacity as basis, 310
noise and, 366
nutrition and, 310, 318, 321
personnel policies and, 319
physiological factors in, 311, 313
problem of, 308
psychological factors in, 311, 313
recreation and, 322
rest pauses and, 317
shift rotations and, 318, 321
transportation of worker as factor in, 317, 321
use of alcoholic beverages and, 322
vacations and, 317, 320
vitamin deficiency and, 329
war conditions and, 308
Federal agencies, nutritional education and, 333
services available from, 39, 40
surveys of community hospital and health facilities by, 14
Federal Government, organization and practice of industrial hygiene in, 109
interdepartmental relationships, 117
Federal Public Housing Authority, services available from, 40
Federal Security Agency, Defense Health and Welfare Services, 40
Female labor, sources of, 396. See also *Women, employment of.*
Fever, metal fume, 145
spotted, community sanitation and, 343
Fibrosis, pulmonary, occupational, 150. See also *Silicosis.*
Filing space in plant infirmary, 19
Films, use of, in health education, 306
Finger dexterity tests for women, 397
First-aid classes, nurse and recommendations on, 82
men, 34
opportunities for health education, 297
post, personnel, duties of, 102
stations, functions of, 69
in plant medical services, 69
location of, 69
Fish and Wildlife Service, Interior Department, 40
Fish packing industries, community sanitation and, 342
Fleas, community sanitation and, 343
Flies, community sanitation and, 343
Floor space, utilization of, illumination and, 354
Floor, workroom, plant sanitation and, 351
Florida, U.S.P.H.S. District including, 14
Fluoride flux, dermatitis from, prevention, 195
salts, in magnesium casting, 239
Fluorides, water pollution from, 338
Fluoroscopic examination in tuberculosis control, 274
Folliculitis, cutting oils and, 176
differential diagnosis, 177
TNT, 192
Follow-up in venereal disease control, 289
Food and Nutrition Board, National Research Council, daily allowance table, 326
Food, community sanitation and, 337
handlers, immunization of, physical examination of, items to be included, 54
respiratory diseases, examination for, 54
streptococcic sore throat, examination for, 54
venereal disease and, overemphasis upon, 53
poisoning, reporting to health authorities, 39
preparation of, in plant cafeterias, 332
Foot drop in lead poisoning, 142
Foot hygiene in athlete's foot, 196
Footcandle requirement, table of, 361, 362, 363, 364, 367
Ford Company, vocational rehabilitation in, 389

- Foremen, kindly interest in worker, 320
- Forge shops, minimum illumination for, 361
- Forging, health hazards of, 231
- Formaldehyde water as aerosol, 271
- Fractures, calcium inadequacy and, 327
- Frequency rates, in sickness absenteeism, 421
- by broad cause and age groups for absences lasting 4 days or more, 443, 444
- by broad cause groups from absences, lasting one calendar day or more, 449, 451
- Fuel availability, temperature and, 373, 374
- Fulminate of mercury. See *Mercury fulminate*.
- Fumes, definition, 198
- diseases caused by, 139
- Fungus infections, occupational dermatitis and, 163, 164
- Furnace lining removal, health hazards of, 231
- Fuses, spring-arming of, protection in, 193
- Fuze cavity reaming, health hazards of, 255
- GALVO, 145
- Gamma rays in luminous dial painting, 237
- in radium, harmful effects, 149
- Garages, mechanical ventilation in, 378
- minimum illumination for, 361
- Garbage disposal, community sanitation and, 342
- Gardens, nutritional education and, 331
- Gas, defense in emergency medical services, 103
- mask, 208
- ammonia, in nitric acid manufacture, 218
- mustard, burns, treatment, 190
- dermatitis caused by, 189
- Gases, definition, 198
- diseases caused by, 139
- war, dermatitis, 188
- Gasoline, tetra-ethyl, in airplane motor cleaning, 215
- toxic limit of, 264
- Gastre-intestinal disorders, rejection rate due to, 384
- General coverage compensation laws, 135
- definitive, 135
- Genito-urinary diseases, rejection rate due to, 384
- Georgia, U.S.P.H.S. District, 14
- Germicides as aerosols, 271
- Glare, accidents and, 356
- direct, 357
- reflected, 358
- results of, 357
- Glass works, minimum illumination for, 362
- Glossitis, vitamin deficiency and, 329
- Glove manufacturing, minimum illumination for, 362
- Gloves, dermatitis prevention and, 169
- for women in industry, 411
- Glycerine nitration, health hazards of, 232
- Glycosuria, rejection rate due to, 384
- selective placement policy and, 390
- Goggles, safety, illumination and, 366
- Gonorrhea, 278. See also *Veneral diseases*.
- employment policy in, 287
- in preplacement examination, 57
- prevalence of, 279
- selective placement policy and, 391
- Granulocytopenia in benzene poisoning, 155
- Grinding, health hazards of, 232
- Grippe, sporadic, 269
- Gums, bleeding, vitamin deficiency and, 329
- blue line on, in mercury poisoning, 148
- lead line on, 142
- HAND coordination tests for women, 397
- Handicapped workers, governmental policy concerning, 388
- limited disability clauses for, 138
- provisions for, in compensation laws, 138
- rehabilitation of, 5, 389
- second-injury funds for, 138
- utilization of, in war industries, 4, 5, 383
- waivers by, 138

- Handicaps, physical, and employment, 44
- Hangars, airplane, minimum illumination for, 362
- Hat manufacturing, minimum illumination for, 362
- Hatters' shakes, 147
- Hawaii, U.S.P.H.S. District including, 14
- Hazards, occupational, 139
 - dental factors in, 88, 90
- Health agencies, private, services offered by, 41
 - public, services offered by, 38-40
- Health authorities, local and State, cooperation with, 39
 - reports of disease to, 39
- Health departments, integrated services, 114
- Health departments, local:
 - development of industrial hygiene work in, 108, 109
 - industrial hygiene units, 116
 - integration of services, importance of, 116
 - organization and practice of industrial hygiene in, 111
 - public health education, 41
 - relationship of plant medical department to, 38
- Health departments, State:
 - development of industrial hygiene work in, 108, 109
 - in control of venereal diseases, 283, 285
 - industrial hygiene divisions, 111
 - chemical functions, 113
 - engineering functions, 113
 - integration of health services, 114
 - medical functions, 112
 - nursing functions, 113
 - public health education, 41
 - types of services possible, 112
 - organization and practice of industrial hygiene in, 111
 - relationship of plant medical department to, 38
- Health education, 297-307
 - choice of physician and, 304
 - compulsory participation not advisable, 300
 - content of workers' program, 301
- Health education, coordination under one program and leadership, 299
 - films in, 306
 - group activities, 299
 - importance of both information and training, 297
 - in combating fatigue, 321
 - individual instruction, 297
 - opportunities for, 297
 - industrial nurse in, duties of, 78
 - integration with community health program, 300
 - materials for, 305
 - medical supervision of, 299
 - meetings, nature and length of, 306
 - motion pictures in, 306
 - photographs in, 306
 - posters in, 306
 - printed materials in, 305
 - distribution of, 305
 - quackery and, 304
 - role of nurse in, 70
 - recommendations, 78
 - self-diagnosis and, 304
 - self-treatment and, 304
 - sources of information to aid in, 41
 - subject-matter of, 301
 - approach to, 303
 - training classes in, 301
 - unofficial organizations active in field of, 124
 - use of treatment time to further, 70
 - workers' committees for, 300
- Health examination, interpretation and recommendations of, in health education, 298
- Health facilities, community, appraisal of, before building war plant, 14
 - in war areas, 2
- Health hazard, cutting oils as, 7
 - electric welding as, 6
 - fatigue as, 7
 - new toxic substances, 7
 - silica sand as, 7
- Health, industrial, women and, 396
 - meaning of, to workers, 298
- Health program, aims, 43
 - first-aid and, 44
 - need for, 43
 - positive, 43
- Health regulations, local, knowledge and observance of, 38

INDEX

481

- Health supervision, first-aid station and, 69
- Hearing, defective, rejection rate due to, 384
- selective placement policy and, 390
- noise and, 386
- war industry as hazard to, 63
- Heart disease, and employment, 44, 60
- as cause of absenteeism, 448, 449
- rejection rate due to, 384
- selective placement policy and, 390, 391
- Heat cramps, salt and, 328
- Heat treating, health hazards of, 233
- Heating, 373-375
- cost, temperature and, 373, 374
- methods, 375
- season, mechanical ventilation in, 377
- Hematopoietic system, changes in, in benzene poisoning, 154
- Hemorrhoids, selective placement policy and, 391
- Hernia, and employment, 44
- rejection rate due to, 384
- selective placement policy and, 390, 391
- Hexyl-resorcinol in propylene glycol as aerosol, 271
- Hidden hunger, 325
- History, occupational, importance of, 140
- of private patient, importance of obtaining, 129
- past, importance in preplacement examinations, 57
- of exposure to irritants, 57
- Hoods, air velocity and equations, 202
- dermatitis prevention and, 169
- ventilation by, 200
- Hospital, effect of priorities on construction, 15
- facilities, community, appraisal of, before building war plant, 14
- plant, 13, 14
- Hospitalization in industrial injuries, 64
- Hospitals, special organization of, in emergency medical services, 104
- Hours of work, optimum, for sustained production, 8, 315
- womanpower and, 400, 402
- Housekeeping, air contamination and, 205
- glycerine nitration and, 232
- in lead pouring, 236
- in nitroglycerine neutralization and washing, 243
- in nitrometer operation, 243
- in sandblasting operations, 214
- plant, 211
- education of workers in, 212
- in ballistics testing, 220
- sanitation and, 351
- Housing, community sanitation and, 339, 340
- facilities, and fatigue problem, 321
- in war areas, 2, 3
- women in industry and, 415
- Hunger, weakness and, 326
- work and, 326
- Hydraulic press operators, dermatitis prevention in, 194
- Hydrocele, rejection rate due to, 384
- selective placement policy and, 390, 391
- Hydrocyanic gas in heat treating, 233
- Hydrofluoric acid, dermatitis from, prevention, 195
- Hydrogen chloride, in pickling, 247
- in soldering, 252
- toxic limit of, 264
- Hydrogen cyanide, in electroplating, 230
- toxic limit of, 264
- Hydrogen fluoride, in magnesium casting, 239
- in welding, 262
- toxic limit of, 264
- Hydrogen sulfide, as skin irritant, 176
- in pickling, 247
- toxic limit of, 264
- Hygiene, industrial. See *Industrial hygiene*.
- Hypertension and employment, 45, 60
- rejection rate due to, 384
- selective placement policy and, 390, 391
- Hypochlorite solution as aerosol, 271

- ICE MAKING, minimum illumination for, 862
- Idaho, joint interdepartmental action in industrial hygiene field, 119
- U.S.P.H.S. District including, 15
- Igniter mixture preparation, health hazards in, 234
- Illinois, U.S.P.H.S. District including, 14
- Illness. See *Sickness*.
- Illuminating Engineering Society, interest in industrial hygiene, 123
- Illumination, adequate, benefits of, 353-
 factors of, 357
 plant, 353-366
 quality of, 357
 recommended minimum standards of, 360
 tabulation, 361-365, 367
- Immunization against colds, 269
- against influenza, 269
- against pneumonia, 270
- Immunizations, need of, 54
- Impetigo contagiosa, occupational dermatitis and, 163
- Incendiary mixture preparation, health hazards of, 234
- Indiana, U.S.P.H.S. District including, 14
- Indigestion, vitamin deficiency and, 329
- Individual, worker as, 292
- Industrial agencies, activities of, in industrial health, 123
- dental consultative service, U. S. Public Health Service, dental services and, 71
- diseases. See *Occupational diseases*.
- fatigue, 308-324. See also *Fatigue*.
- health, activities of nonofficial agencies in, 122
- Industrial Health Research Board, optimum hours of work in munitions factories, 316
- Industrial hygiene, available services in, 106-130
- birth of, during World War I, 107
- clinics, in small plant organization, 58
- development of, in United States, 107
- Industrial hygiene, development of, units in State and local departments of health, 108, 109
- divisions, local, 117
- responsibilities of, 119
- State, 111
- chemical functions, 113
- dental services, 90
- engineering functions, 113
- integration of health department services by, 114
- medical functions, 112
- nursing functions, 113
- organization and practice of, 111
- types of services possible, 112
- war assistance by Division of Industrial Hygiene, 125
- U. S. Public Health Service, 109
- utilization of services of, by physicians, 129
- early development, 107
- in war effort, 124, 127
- institutes on, conducted by medical profession, 128
- new philosophy of, 130
- organization and practice of, 109
- in State and local health departments, 111
- in U. S. Public Health Service, 109
- integrated services, 114
- interdepartmental relationships, 117
- place in public health program, 122
- problems in, where to report, 39
- preliminary surveys advocated by U.S.P.H.S., 109
- professional personnel problem, 9, 10
- programs, Federal, 75
- Federal assistance available, 75
- State, 76
- State assistance available, 75
- State, nursing consultation services, scope of, 76
- role of dentist in, 90
- war's influence on, 1-11

INDEX

483

- Industrial Hygiene Foundation of America, 123
- Industrial injuries to women, absenteeism and, 413
- Industrial medicine, place of psychiatry in, 292
- Industrial nurse, absenteeism and, role in decreasing, 78
- accident control program and, 71
- prevention program and, recommended activities, 79
- American Red Cross Home Nursing classes and recommendations on, 82
- duties of, 67, 68
- at first aid station, 69
- at medical examination, 70
- recommended participation, 78
- blood pressure readings, 70
- examinations for evidence of occupational disease, 78
- health education program, recommended activities, 78
- hearing test, 70
- inspections and interviews on return to work permits, 78
- preexamination interview, 70
- procuring specimens for laboratory examination, 70, 78
- recommendations of the Committee to Study the Duties of Nurses in Industry, 77
- vision test, 70
- with full-time physician, 69
- with "on call" physician, 68, 69
- with part-time physician, 68
- written standing orders for, recommendations on, 77
- health education and, recommended activities, 78
- home nursing and, recommendations on, 81
- visiting service, 72
- inspection of sanitary facilities, 71
- nonmedical work, recommendations against, 81
- part-time basis, in small plants, recommendations on, 85
- plant protection plans and, recommendations on, 82
- procurement of, professional channels for, recommendations on, 85
- Industrial nurse, proportion of, to plant employees, recommendations on, 84
- qualifications, academic, recommendations on, 82
- membership in professional organizations, recommendations on, 83
- personal, recommendations on, 82
- professional, recommendations on, 83
- records and reports, recommended activities in, 80
- role in health education program, 70
- salary of, recommendations on, 83
- sanitation and, recommended activities, 79
- supervision of, recommendations on, 80
- training of, 73
- use of, most effective, 84
- welfare program and, 72
- recommended activities, 79
- Industrial nursing, scope of, 67
- supervision of, 74
- Industrial output, optimum hours of work and, 315
- Industrial physician, 28
- administration of psychiatric program by, 293, 295
- community sanitation and, 336
- conference of worker with, in venereal disease control, 288
- demands of war conditions on, 8
- difficulty in securing, 28
- number required, 30
- private practice by, 29
- qualifications, recommendations of American College of Surgeons, 30
- reporting of venereal diseases by, 289
- role of, in combating fatigue, 322
- in venereal disease program, 284
- with employees, 49
- shortage of, as wartime problem, 9
- use of part-time consultants, 29
- Industrial plant protection, organization of, 101

- Industrial poisoning, portals of entry, 140
 - predominance of, among industrial diseases, 140
- Industrial psychiatry, 291-296. See also *Psychiatry, industrial*.
- Industrial wastes, water pollution and, 338
- Industry, community sanitation and, 337
 - objectives of venereal disease program, 282
 - psychiatric bulk in, classification, 294
 - percentage of total employees, 294, 295
 - venereal disease problem in, 279, 280
- Infections, respiratory, acute, 267
- Infectious agents, diseases caused by, 139
 - diseases in food handlers, examination for, 54
- Infirmery, plant, 12
 - ambulance and equipment, 22
 - architectural fundamentals of, 12
 - avoiding overbuilding, 18
 - control point, 18
 - essential features of, 17
 - examination rooms, 21
 - eye examining room, 20
 - treatment room, 20
 - filing space, 19
 - functions of, 17
 - laboratory of, 21
 - location of, 15
 - office space, 23
 - operating rooms, 19
 - physiotherapy apparatus, 22
 - planning construction of, 12
 - rest rooms and wards, 20
 - size and type of, 15
 - storage space, 23
 - substations, 17, 23
 - rest rooms in, 21
 - toilets, 22
 - treatment rooms, 19
 - versus hospital, 13
 - waiting rooms, 18
 - X-ray facilities, 22
- Influenza, endemic, 269
 - epidemic, 269
 - etiology, 269
 - general control measures, 271
 - pandemic, 269
- Influenza, prophylaxis of, 269
- Infra-red machine in plant infirmery, 22
 - radiation, from drying lamps, 369, 371
 - in welding, 262, 369
 - protection against, 369
- Injuries, industrial, as cause of absenteeism, 413, 427, 438, 439, 440
 - hospitalization and, 64
 - treatment of, 64
 - nonindustrial, as cause of absenteeism, 413, 427, 433, 438, 439, 440, 442, 444, 445, 447, 449, 450, 451, 452, 453, 454
 - nonoccupational, plant medical services and, 64
- Inorganic requirements, dietary, 327
- Insect control, community sanitation and, 343
- Inspection, minimum illumination for, 362
 - of war plants, 125
- Instrument manufacture, air conditioning in, 379
 - health hazards of, 379
- Insulation, noise and, 368
- Insurance companies, industrial health activities of, 124
 - public health education by, 41
 - compensation, 136
 - department or carriers, relationship of medical department to, 37
- Integration of health department services, local, 116
 - State, 114
- Intelligence tests for women, 397
- Interdepartmental relationships, joint action and, 117
- Interview, therapeutic value of, 295
- Iodine deficiency, 328
 - requirements, dietary, 327
- Iowa, institutes on industrial health, conducted by medical profession, 128
 - U.S.P.H.S. District including, 15
- Iron, dietary, recommended daily allowance, 329
 - requirements of, 327
 - sources of, 327
 - manufacturing, minimum illumination for, 362
- Irritability, hunger and, 326
- Irritants, dermatitis and, 162

Irritants, detoxifying ointment for, formula, 171
 repelling ointment for, formula, 171
 skin, hydrogen sulfide as, 176
 sulfur dioxide as, 176
 specific, dermatitis due to, 175
 Isolation in colds, 272

JAW, necrosis of, in radium poisoning, 149

Jewelry, hazard of, in industry, 412
 manufacturing, minimum illumination for, 362

Job, analysis, 387, 391.
 womanpower and, 398
 engineering, for maximum efficiency, 320

rotation, in monotonous work, 320
 training of employee in, 320

Jurisdictions in which occupational disease is compensated, with addresses of administrative agencies, 132, 138

KANSAS, U.S.P.H.S. District including, 15

Kentucky, U.S.P.H.S. District including, 14

Kerosene dermatitis, 193

Kessler, Henry H., 385

Kitchen, minimum window requirement for, 376

Koroseal as-dermatitis preventive, 168

LABOR force of war industries, 3

Labor Standards, Division of, U. S. Department of Labor, 40, 108

Labor unions, relationship of medical department to, 36

Laboratories, State, reliance on, by plant medical department, 39

Laboratory of plant infirmary, 21
 technicians, 34

tests, physical examination and, 46

Lamps, drying, infra-red radiation from, 369, 371

mercury vapor, ultraviolet radiation from, 369, 371

Latent period in occupational diseases, 140

Laundry, in skin-contaminating occupations, 350

minimum illumination for, 362

Lead, atmospheric, in bullet casting, 234

aside, 45

and physical examination, frequency of, 51

dermatitis, 187

bullet casting, health hazards of, 234

burning, health hazards of, 235

colic, 142

commonly used compounds, 141

cumulative, in tissues, 141

dental services and, 90

dust, in ballistics testing, 219

in grinding, 232

in lead melting, 235

in lead pouring, 236

encephalopathy, 143

differential diagnosis, 144

fumes, in lead melting, 235

in lead pouring, 236

in metal spraying, 240

in shell case manufacture, 251

in soldering, 252

in brush painting, 244

in cold tinning process, 224

in spray painting, 245

in welding, 262

industrial uses of, 141

line, gingival, 142

differential diagnosis, 142

maximum permissible concentration in air, 141

melting, health hazards of, 235

molten, and physical examination, frequency of, 51

neuropathy, 142

differential diagnosis, 144

paralysis, 142

poisoning, 141-145

alimentary type, 142, 144

blood and urine concentrations, 143, 144

blood picture in, 143

differential diagnosis, 144

encephalopathic type, 143, 144

laboratory findings, 143

neuromuscular type, 142, 144

prevention, periodic check-ups for, 145

return to occupation after recovery, 144

symptoms, 141

treatment, 144

portals of entry, 141

pouring, health hazards of, 236

- Lead, tetraethyl, and physical examination, frequency of, 51
 thiocyanate, in primer mixture screening, 248
 toxic limit of, 264
 water pollution from, 338
 white, in machinery, 239
- Learning, retarded, vitamin deficiency and, 329
- Leather cleaning, health hazards of, 236
 manufacturing, minimum illumination for, 362
 working, minimum illumination for, 362
- Leg, loss of, and employment, 44
- Legal department, relationship of medical department to, 36
 restrictions, womanpower and, 400
- Legislation, compensation. See *Compensation laws*.
 on employment during pregnancy, 407
 on weight lifting by women, 408
- Lens cleaning, health hazards of, 236
- Lewisite dermatitis, 190
- Liability, accrued, 137
- Lice, community sanitation and, 343
- Lichen planus, occupational dermatitis and, 163
- Life insurance companies. See *Insurance companies*.
- Light, color quality of, 359
 diffusion of, 358
 distribution of, 358
 quantity of, 359
 visible, radiation from welding arc, 369
- Lighting, plant, 353. See also *illumination*.
- Lime, dermatitis caused by, 163
- Limited disability clauses in compensation laws, 138
- Line oil dermatitis, 194
- Living conditions of war workers, 2, 3
- Local health departments; development of industrial hygiene work in, 108, 109
 industrial hygiene units, 116
 integration of services, importance of, 116
 organization and practice of industrial hygiene in, 111
 public health education, 41
- Locker rooms, minimum illumination for, 362
 minimum window requirement for, 376
- Louisiana, U.S.P.H.S. District including, 14
- Luminous dial painting, health hazards of, 237
 paints, poisoning from, 149
- Lunch periods, length of, 319, 321, 332
 for women workers, 404
- Lunch, supplementary, 326
- Lunchroom, specifications, 351
- Lungs, dust affections of, 150. See also *Silicosis*.
- MACHINE, placement of, air contamination and, 207
 shops, minimum illumination for, 362
- Machinery, noise and, 368
- Machining, health hazards of, 239
- Magna flux, dermatitis prevention from, 195
- Magnesium casting, health hazards of, 239
 gas gangrene, 194
 requirements, dietary, 327
 screening, health hazards of, 261
- Maine, U.S.P.H.S. District including, 14
- Maladjusted in industry, 294, 295
- Malaria, community sanitation and, 343
 in preplacement examination, 57
- Malingering, binocular test and, 62
 control of, in sickness absenteeism, 52, 423
- Malnutrition, 329
 as cause of absenteeism, 318
 in industry, 325
- Management, cafeterias owned by, 333
 night shift and, 402
 relationship of medical department to, 25, 35
 responsibilities of, in air contaminant control maintenance, 211
 in plant housekeeping, 212
 role of, in nutritional education, 332
- Manganese, industrial uses of, 147
 poisoning, 147
 control of, 147

INDEX

487

- Manganese, poisoning, differential diagnosis, 147
 - symptoms, 147
 - water pollution from, 338
- Manpower, job analysis and, 387, 391
 - maximum use of, 383-394
 - general considerations, 386
 - job analysis and, 387, 391
 - need for war industries, 3
 - problem, 383-466
 - selective placement policy, 390
- Maryland, U.S.P.H.S. District including, 14
- Massachusetts, U.S.P.H.S. District including, 14
- Maternity leave, 404
- Maximum benefit period, effect of, on sickness absenteeism rates, 422, 424, 455
- Meal frequency, 326
 - nutrition and, 326
 - periods, length of, 319, 321
- Meat packing, minimum illumination for, 362
- Mechanical rubber goods manufacturing, minimum illumination for, 364
- Medical benefits under compensation laws, 136
- Medical control measures, benzene poisoning, 155
 - lead poisoning, 145
 - manganese poisoning, 147
 - metal fume fever, 146
 - radium poisoning, 150
 - respiratory diseases, 267-277
 - silicosis, 154
- Medical department, plant, administration of, 25
 - ambulance men, 34
 - clinic assistants, nonprofessional, 33
 - conclusions regarding, 42
 - consultants, 31
 - part-time, 29
 - costs of, 27
 - dentists, 32
 - departmental authority, 25
 - first-aid men, 34
 - functions of, 17, 25
 - laboratory technicians, 34
 - medical director, 27
 - full-time or part-time, 28
 - qualifications of, 28
 - nurses in, 32
- Medical department, nurses in, limit on clerical duties, 33
 - number required, 32
 - nursing supervisor, 32
 - qualifications of, 32
 - organization of, 25-42
 - personnel of, 27
 - physical equipment, 12-24
 - physicians, 28
 - difficulty in obtaining, 28
 - number required, 30
 - part-time, 29
 - private practice by, 29
 - qualifications of, 30
 - recommendations of American College of Surgeons, 30
 - physiotherapy aides, 34
 - position of branch establishments, 26
 - practical nurses in, 33
 - relationship to cafeteria, 37
 - to coroner's or medical examiner's office, 38
 - to insurance department or carriers, 37
 - to labor unions, 36
 - to legal department, 36
 - to local health department, 38
 - to Office of Civilian Defense, 40
 - to other plant activities, 35
 - to outside agencies, 38
 - to personnel department, 35
 - to private agencies, 41
 - to safety department, 36
 - to State health department, 38
 - to top management, 35
 - to U. S. Public Health Service, 39
 - to various Federal agencies, 40
 - to welfare department, 37
 - reports of diseases, 39
 - of industrial hygiene problems, 39
 - sources of information for programs of health education, 41
 - X-ray technicians, 34
- Medical director, plant, 27
 - full-time or part-time, 28
 - parity with plant officials, 25

- Medical director, plant, qualifications of, 28
relationships with private agencies, 41
responsibility to top management, 25
- Medical examiner's office, relationship of plant medical department to, 38
- Medical facilities, plant, 12-24
in war areas, 2
- Medical functions of State industrial hygiene division, 112
- Medical profession, responsibilities of, 126, 129
utilization of services of industrial hygiene divisions by, 129
war effort in field of industrial hygiene, 126
- Medical records, 55. See also *History*.
confidential nature of, 286
examination, 56
for periodic examination, 57
form of, 56
detail required, 56
preplacement examination, 56
- Medical rehabilitation, 389
- Medical services, 43-65. See also *Health program, Dental program, and Nursing services*.
emergency, ambulance service, organization of, 102
casualty station, organization of, 100
cooperation with civilian authorities, 98
first aid posts, organization of, 102
gas defense, 103
hospitals, special organization of, 104
nursing services in, 100
plant defense coordinator, duties of, 100
stretcher teams, organization of, 102
within plant, 99
integration with those of community, 98-105
organization of, 99, 103
emotional problems and, 63
executive of, to whom responsible, recommendations on, 83
function of, 44
- Medical services in small plants, organization of, 58
inclusion of venereal disease control, 234
industrial nurse in, on part-time basis, recommendations on, 85
optometrists in, 62
plant, manpower and, 400
psychiatric problems and, 63
relation to plant as a whole, recommendations on, 83
treatment, 64
under compensation laws, time limits of, 136
- Medical societies, affiliation with, 41
- Medical Unit, Division of Industrial Hygiene, National Institute of Health, 110
- Meetings, health education, nature and length of, 306
- Menstrual disorders, industrial physician and, 407
- Mental diseases, rejection rate due to, 384
health of workers, 291-296
- Mental Hygiene Association, 41
- Mentality, subnormal, and employability, 294
- Mercurialism, 148
- Mercury, atmospheric, in cold tinning process, 224
crack testing, health hazards of, 239
dental services and, 90
fulminate, 45
and physical examination, frequency of, 51
dermatitis, 148, 186, 193
diagnosis, 186
dermatosis due to, 148
in welding, 262
industrial uses of, 147
mining of, as hazard, 147
poisoning, 147
symptoms, 148
toxic limit of, 264
vapor lamps, ultraviolet radiation from, 369, 371
vapors, in nitrometer operation, 243
in pellet density testing, 247
- Metal cleaning, health hazards of, 247
- finishing, health hazards of, 240
fume fever, 145

- Metal fume fever, control of, 146**
 differential diagnosis, 146
 immunity to, 146
 symptoms, 145
 preservatives, dermatitis from, 181
 shakes, 145
 spraying, health hazards of, 240
Metalizing, health hazards of, 240
Metallic dusts in grinding, 232
 salts in electroplating, 229
Metalloids, toxic, diseases caused by, 139
Metals, toxic, diseases caused by, 139
Methyl alcohol, in type cleaning, 248
 toxic limit of, 264
Methyl ethyl ketone in rubber goods fabrication, 249
Michigan, U.S.P.H.S. District including, 14
Migration, community sanitation and, 343
Military objectives, industrial plants as, emergency medical services in, 98
Milk control, community sanitation and, 337, 341
 precautions in, 341
 in dietary, 327
 pasteurization, 341
Milling, grain foods, minimum illumination for, 362
Mineral dust, lung affections due to, 150. See also Silicosis.
Miniature x-ray films in chest surveys, 274
Minnesota, U.S.P.H.S. District including, 15
Mississippi, U.S.P.H.S. District including, 14
Missouri, U.S.P.H.S. District including, 15
Mists, definition, 198
Monochlorobenzene, toxic limit of, 264
Mononitrotoluene, in toluene nitration, 260
 toxic limit of, 264
Montana, U.S.P.H.S. District including, 15
Moral persuasion in control of absenteeism, 462
Morale as factor in absenteeism, 463
 illumination and, 355
Morbidity reporting, in venereal diseases, 289
Mortar shell loading, dermatitis and, 191
Mosquitoes, community sanitation and, 343
Motion pictures, use of, in health education, 306
Motor testing, health hazards of, 241
Mucosa, nasal, mercury fulminate irritation in, 186
 protection in electroplating, 182
 in welding, 182
Munitions plants applications, rejection rate of, 384
Muscular efficiency, 326
Mustard gas, 189
Mycosis, industrial dermatitis and, 164
NAPHTHA, petroleum, in rubber goods fabrication, 249
 in type cleaning, 248
Naphthalenes, dermatitis caused by, 163
Naphthas, toxic limit of, 264
National Association of Manufacturers, costs of medical program, 27
 Committee on Healthful Working Conditions, 123, 385
National Dairy Council, nutritional education and, 333
National Industrial Conference Board, costs of medical program, 27
 interest in industrial hygiene, 123
National Institute of Health, Division of Industrial Hygiene, 10, 39, 109
 duties of, 75
 fields of work in war effort, 125
 organization chart, 110
 public health education, 41
 services offered by, 39
 study of fatigue in truck drivers, 311
National Institute of Health, Nutrition Section, Division of Chemotherapy, 41
 nutritional education and, 333
National Nursing Council for War Service, distribution of nursing service, recommendations on, 84
National Red Cross, nutritional education and, 333

- National Research Council, Food and Nutrition Board, daily allowance table, 326
- National Safety Council, interest in industrial hygiene, 123
mechanical aids for women, 408
services offered by, 41
- National Tuberculosis Association, health education, 41
interest in industrial hygiene, 123
- Nebraska, U.S.P.H.S. District including, 15
- Necrosis of jaw in radium poisoning, 149
- Negroes, sickness absenteeism among, 435
skin sensitivity in, 197
- Nervous breakdown, in preplacement examination, 57
diseases, as cause of absenteeism, 448, 449
rejection rate due to, 384
system, glare and, 357
- Neurodermatitis, occupational dermatitis and, 163
- Neurologic symptoms in manganese poisoning, 147
- Neuromuscular type of lead poisoning, 142, 144
- Neuropathy, lead, 142
differential diagnosis, 144
- Neuropsychiatric conditions in industrial workers, 294
- Neuroses, noise and, 366
- Nevada, U.S.P.H.S. District including, 14
- New Hampshire, U.S.P.H.S. District including, 14
- New Jersey, activities of medical profession in furthering wartime program of industrial hygiene, 128
physical rehabilitation in, 390
Rehabilitation Clinic, 385
U.S.P.H.S. District including, 14
- New Mexico, U.S.P.H.S. District including, 15
- New York, U.S.P.H.S. District including, 14
- Nicotinic acid, recommended daily allowance, 329
- Night work, womanpower and, 401, 402
- Nitration, dimethylaniline sulfate, 228
DMAS, health hazards of, 241
- Nitric acid, manufacture, health hazards in, 218
tank filling, health hazards in, 215
- Nitro compounds, skin sensitization by, 162
- Nitrobenzene, distillation, health hazards of, 242
in benzene nitration, 221
neutralization, health hazards of, 242
reduction, health hazards in, 219
separation, health hazards of, 242
storage, health hazards of, 242
toxic limit of, 264
- Nitrocellulose cutting, health hazards of, 242
graining, health hazards of, 242
- Nitrogen, oxides of, in ballistics testing, 219
in DMAS nitration, 241
in glycerine nitration, 232
in nitric acid manufacture, 218
in nitric acid tank filling, 215
in nitrometer operation, 243
in pickling, 247
in toluene nitration, 260
in welding, 262
toxic limit of, 264
- Nitroglycerine, in glycerine nitration, 232
neutralization health hazards of, 243
washing, health hazards of, 243
- Nitrometer operation, health hazards in, 243
- Nitroso compounds, skin sensitization by, 162
- Noise, 366-369
elimination at source, 368
insulation and, 368
isolation and, 368
personal protective devices and, 369
plant, 366-369
- Nonofficial agencies, activities of, in industrial health, 122
- Nonrespiratory-nondigestive diseases as cause of absenteeism, 427, 428, 433, 437, 438, 440, 444, 445, 446, 447, 448, 448, 449, 450, 451, 452, 453, 454
- North Carolina, joint interdepartmental action in industrial hygiene field, 119

- North Carolina, U.S.P.H.S. District including, 14
- North Dakota, U.S.P.H.S. District including, 15
- Notification, method of, as factor in sickness absenteeism rates, 423
- Nurse, community, home nursing and, 73
- in industry, special functions of, 66
- industrial. See *Industrial nurse*.
- practical, in plant medical department, 33
- public health, in industry, duties of, 75
- role in physical examination, 47
- when toxic substances involved, 50
- in plant medical services, 67
- senior, in industry, duties of, 75
- supervisor, in industry, duties of, 74-75
- visiting. See *Visiting nurse*.
- Nursing, industrial, scope of, 67
- supervision of, 74
- Nursing functions of State industrial hygiene divisions, 113
- Nursing services, 66-87. See also *Medical services*.
- acceptable practices, recommendations for, by Committee to Study the Duties of Nurses in Industry, 77
- accident control program, nurse's role in, 71
- accident prevention, assistance with, recommendations on, 78
- activities of industrial nurse, 68
- American Red Cross Home Nursing classes, nurse and, recommendations on, 82
- caution against denuding community of nurses, 33
- community nurse and, cooperation with, 73
- duties outside medical department, 81
- Federal industrial hygiene programs, assistance available, 75
- first-aid classes, nurse and, recommendations on, 82
- health education program, nurse's role in, 70
- participation in, recommendations on, 78
- home nursing services, nurse's role in, 72
- Nursing services, home nursing services, recommendations on, 81
- in small plant, on part-time basis, recommendations on, 85
- industrial hygiene programs, Federal, 75
- State, scope of, 76
- industrial nurses, supervision of, 74
- limit on clerical duties of personnel, 33
- medical department, maintenance of, 68
- medical examinations, assistance with, 70
- recommendations on, 78
- nonoccupational illnesses, emergency care, 69
- nonprofessional assistants, recommendations on, 81
- number of nurses required, 32, 84
- nurses in, per employee unit, 84
- qualifications of, academic, and recommendations on, 82
- membership in professional organizations, recommendations on, 83
- personal, recommendations on, 82
- professional, recommendations on, 83
- salary, recommendations on, 83
- occupational illnesses, nursing care in, 69
- injuries, nursing care in, 69
- practical nurses in, 33
- plant protection plans, nurse and, recommendations on, 82
- procurement of, professional channels for, recommendations on, 85
- recommendations for, summary statement of, 86
- records and reports, industrial nurse and, recommended activities, 80
- recommendations on, 80
- role in emergency medical services, 100
- safety education, assistance with, recommendations on, 79
- nurse's role in, 71

- Nursing services, sanitation, assistance with, recommendations on, 79
 environmental, nurse's role in, 71
 scope of industrial nursing, 67
 State industrial hygiene programs, assistance available, 75, 76
 supervision of, 74
 of nurses in industry, recommendations on, 80
 technical services, special, recommendations on, 81
 welfare program, nurse's role in, 72
 Recommendations on, 79
 written standing orders, 77
- Nursing societies, activities of, in industrial health, 124
- Nursing supervisor, plant, 32
- Nutrition, as factor in fatigue, 310, 318, 321
 education and, 331
 in industry, 325-334
 improvement of, 330
 of war workers, 8
 unofficial organizations active in field of, 124
- Nutritionists, plant, 35
- OAKITE dermatitis, 193
- Occupation, effects of, on sickness absenteeism, 434
- Occupational dermatoses. See *Dermatitis*.
- Occupational diseases, 64, 131
 absenteeism in women and, 413
 clinical descriptions of, 139
 compensation costs of different types, comparison of, 131
 compensation laws, 135
 types of, 135
 definition of, 134
 dental factors and, 89, 90
 history, importance of, 140
 jurisdictions where compensated, with addresses of administrative agency, 132, 133
 latent period, 140
 liability of employer, 131, 132
 major groups, 139
 medical questions arising, 140
 need for knowledge of, by private physicians, 129
- Occupational diseases, predominance of industrial poisoning, 140
 prevention and control of, 131-382
 problem of, 131-160
 conclusions regarding, 157
 reporting of, 119, 129
 time factor, importance of, 140
 war industries and, 139
- Occupational hazards, 139
- Occupational history, importance of, 140
 of private patient, importance of obtaining, 129
- Occupational pulmonary fibrosis, 150. See also *Silicosis*.
- Occupations forbidden to women, 401
- Office, minimum illumination for, 362
 minimum window requirement for, 376
 space in plant infirmary, 23
- Office of Civilian Defense, relationship of plant medical department to, 40
- Office of Defense Health and Welfare Services, nutritional education and, 41, 333
 program for care of children of working mothers, 417
 Subcommittee on Industrial Health and Medicine, 125
- Official agencies, formulation of rules and regulations, 120
 investigation and enforcement of rules, 120
 present organization and practice of industrial hygiene in, 109
 relationships with private agencies, 119
 reporting of occupational diseases, 119
 responsibilities of, 119
 services offered by, 38-40
 types of health service possible, 112
 war organization, 124
 work of, in field of industrial medicine, 108
- Ohio, U.S.P.H.S. District including, 14
- Oil cloth as dermatitis preventive, 168
- Oils, animal, dermatitis and, 176
 cutting, as health hazard, 7

INDEX

493

minance
g, 140
of, 131-

157

of, 140

ance of,

ortance

fibrosis,

en, 401

for, 362

ent for,

lation-

rtment

d Wel-

itional

333

f chil-

others,

ustrial

ne, 125

on of

20

ement

prac-

ne in,

agen-

l dis-

ssible,

strial

ding,

ative,

76

Oils, cutting, dermatitis and, 175
treatment, 178
vegetable, dermatitis and, 176
Ointment, dermatitis and, 169
"invisible glove," formula, 170
preventive, against tetryl, 183
protective, formulas, 170-172
Oklahoma, U.S.P.H.S. District in-
cluding, 15
Operating rooms of plant infirmary, 19
Operations, surgical, in preplace-
ment examinations, 57
Ophthalmologist, role in medical
services, 62
Optometrists, role in medical serv-
ices, 62
Oregon, U.S.P.H.S. District includ-
ing, 14
Organization and operation of facili-
ties, 1-130
and practice of industrial hygiene,
109
in State and local health
departments, 111
in U. S. Public Health Serv-
ice, 109
integrated services, 114
inter-departmental relation-
ships, 117
of plant medical department, 25
Orthopedic defects, rejection rate
due to, 384
selective placement policy and,
390, 391
Osteitis, radiation, 149
Overtime, as factor in sickness ab-
senteeism, 456
fatigue and, 8
Oxide chills, 145
Oxides of nitrogen. See *Nitrogen*,
oxides of.
Oxygen, administration of, in carbon
monoxide poisoning, 156
PACKING, minimum illumination for,
363
Paint, asphalt, dermatitis caused by,
193
camouflage, manufacture, health
hazards in, 223
drying, health hazards of, 244
luminous, poisoning from, 149
mixing, minimum illumination for,
363
shops, minimum illumination for,
363

18

Paint thinners, dermatitis from,
179, 180
prevention, 180, 195
Painting, brush, health hazards of,
244
spray, health hazards in, 245
Paper box manufacturing, minimum
illumination for, 363
Paper manufacturing, minimum il-
lumination for, 363
Papillomata, cutting oils causing,
177
Paralysis in lead poisoning, 142
Paratyphoid fever, examination for,
in food handlers, 54
Passageways, minimum illumination
for, 364
Pasteurization, milk, 341
Patch test, in dermatitis, 165
techniques, 166
for cutting oil, 178
for explosives, 193
for lead azide, 188
for mercury fulminate, 187
for paint, 180
for tetryl, 183
for TNT, 185
Patriotism, appeal to, in control of
absenteeism, 463
Pellagra, 329
Pellet density testing, health haz-
ard of, 247
Penalty provisions in compensation
laws, 137
Pennsylvania, U.S.P.H.S. District
including, 14
Personal hygiene, possible services
by health department in, 114
reasons for absenteeism, 458
control of, 462
Personalities, psychopathic, among
industrial workers, 294
unstable, upset by war, 294
Personnel, department of, relation-
ship of medical department to,
35
of plant medical department,
27
policies as factor in fatigue,
319
problems of, dermatitis and, 196
recruitment and training by Divi-
sion of Industrial Hygiene,
125
shortage among industrial physi-
cians, 9

- Petroleum, distillates, dermatitis caused by, 163
 naphthas, toxic limit of, 264
 spirits, dermatitis from, 193
 toxic limit of, 264
- Phenolic resin in wood veneer processing, 263
- Phosgene, toxic limit of, 264
- Phosphine, in pickling, 247
 toxic limit of, 264
- Phosphorus, dental services and, 90
 milk as source of, 327
 requirements, dietary, 327
- Photo engraving, minimum illumination for, 363
- Photofluorographic units, U. S. Public Health Service, 274
- Photofluorography in tuberculosis control, 274
- Photographs, use of, in health education, 306
- Physical agents, diseases caused by, 139
- Physical disability, workers with. *See Handicapped workers.*
- Physical examination. *See also History and Medical records.*
 aims of, 44
 annual, 49
 of employees over forty, 49
 value of, 49
 arterial hypertension and, 60
 at termination of employment, when advisable, 53
 beyond strict scope of employment, when indicated, 53
 discussion of, with employee, 48
 extent of, 45
 following illness, 52
 frequency of, in ammonium picrate exposure, 51
 in benzene exposure, 51
 in DNT exposure, 51
 in key workers, 51
 in lead azide exposure, 51
 in lead exposure, 51
 in mercury fulminate exposure, 51
 in radium exposure, 51
 in tetryl exposure, 51
 in TNT exposure, 51
 in toluene exposure, 51
 heart disease and, 59
 immunization at time of, 155
 items to include, 46
 laboratory tests to include in, 46
- Physical examination, nurse in, role of, 50
 of construction workers, 48
 of employees exposed to toxic substances, 50
 frequency, 51
 items to include, 50
 nurse in, 50
 of eye, 61
 of food handlers, 53
 items to include, 54
 of transient employees, 48
 items to include, 48
 of women, 398
 pelvic examination omitted, 47
 special considerations in, 47
 on request of employee, when indicated, 53
 organization of, 46
 periodic, 49
 dental, 94
 exposure to toxic substances and, 57
 in dusty trades, 154
 in prevention of benzene poisoning, 155
 of lead poisoning, 145
 of manganese poisoning, 147
 in radium-using industries, 150
 in venereal disease control, 287
 opportunities for health education at, 297
 preexamination interview, duties of nurse in, recommended activities, 78
 preplacement, 44
 dental, 94
 extent of history needed, 57
 in control of acute respiratory infections, 272
 opportunities for health education at, 297
 record for, 56
 specific diseases to consider, 57
 venereal disease tests at time of, 282, 287
 records for, 55
 relation to correctable defects, 48
 report on, to other departments, 55
 role of nurse in, 70

- role
- toxic
- 0
- 1, 47
47
then
- ices
- poi-
- ng,
- ies,
- ol,
- lu-
- lu-
ed
- ry
- u-
- r.
- ic
- s.
- s,
- Physical examination, syphilitic aor-
titis and, 60
tuberculosis and, 59
valvular disease and, 60
venereal disease and, 49, 282,
287
Physical rehabilitation, 389
Physical standards, for employment,
44
Physician, and plant inspection, 50
choice of, 304
emotional problems and, 63
family, in combating fatigue, 323
industrial. See *Industrial physi-
cians*.
part-time, in small plant organiza-
tion, 58
plant. See *Industrial physician*.
private, need for knowledge of oc-
cupational diseases by, 129
psychiatric problems and, 63
responsibility of, in industrial hy-
giene program during war, 126,
129
role in plant sanitation, in pres-
ence of industrial poisons, 50
Physiological factors in fatigue, 311,
313
Physiotherapy aides, 34
apparatus of plant infirmary, 22
Phytid(s), industrial dermatitis
and, 164
Pickling, health hazards in, 247
Picric acid, -water pollution from,
338
Pityriasis rosea, occupational derma-
titis and, 163
Plague, community sanitation and,
343
Plant, committee on venereal disease
control, 283
defense coordinator, duties of, in
emergency medical services, 100
facilities, womanpower and, 398
hospital, 13, 14
housekeeping, 205, 212
in sandblasting operations, 214
of penetration ranges, 220
worker education in, 212
industrial, community sanitation
and, 336
infirmary, 12. See also *Infirmary,
plant*.
layout, air contamination and, 201
medical department. See *Medical
department, plant*.
- Plant, medical facilities, 12-24
need for eating facilities in, 8
nutritionists, 35
physician, 28. See also *Industrial
physician*.
sanitation, 345-352
womanpower and, 399
small, provision of medical service
in, 10
surveys, participation in, by plant
physicians, 129
war, appraisal of community hos-
pital and health facilities be-
fore building, 14
inspection of, 125
welfare program. See *Welfare pro-
gram*.
- Plating, minimum illumination for,
363
Pliofilm as dermatitis preventive,
168
Plumbism. See *Lead poisoning*.
Pneumoconiosis, 150. See also *Sili-
cosis*.
classification, 151
definition, 150
dusts producing, respirator for,
231
mixed forms, 151
simple benign, 151
Pneumonia, general control meas-
ures, 271
prophylaxis of, 270
Poisoning, benzene, 154. See also
Benzene poisoning.
cadmium, 146
carbon monoxide, 156
industrial, portals of entry, 140
predominance of, among occupa-
tional diseases, 140
lead, 141-145. See also *Lead poi-
soning*.
manganese, 147
mercury, 147
radium, 148-150. See also *Radium
poisoning*.
Poisons, industrial, 45
and periodic examination, 57
dental factors, 89, 90
DNT, 45
employees exposed to, physical
examination of, 50
to exclude from contact with,
45
lead azide, 45
mercury fulminate, 45

- Poisons, industrial, physical examination of employees exposed to, 50
 tetryl, 45
 TNT, 45
- Polishing, minimum illumination for, 363
- Polychromatophilia in lead poisoning, 143
- Polyvitamins, distribution of, 330
- Pontoon manufacture, health hazards of, 249
- Posters, use of, in health education, 306
- Potassium requirements, dietary, 327
- Powder, black, dermatitis, 188
 smokeless, cutting and graining, health hazards of, 242
 dermatitis, 188
- Power plants, minimum illumination for, 363
- Practical nurses in plant medical department, 33
- Precision war equipment, minimum illumination for, 367
- Preemployment examinations. See *Physical examination, preplacement.*
- Pregnancy, women in industry and, 405
- Preplacement examination. See *Physical examination, preplacement.*
- Preserving, minimum illumination for, 361
- Pressing, minimum illumination for, 361
- Prevention of occupational diseases, 131-382
- Prices, food, in plant cafeterias, 331
- Primer loading, protection in, 191
- Primer manufacture, dermatitis in, 186, 187
 mercury fulminate dermatitis, 193
 mixture screening, health hazards of, 248
- Printed materials for health education, 305
 distribution of, 306
- Printing, health hazards in, 248
 minimum illumination for, 363
- Priorities, hospital construction and, 15
- Private agencies, services available from, 41
- Private practice by plant physicians, 29
- Product control, conditioning for, 379
- Production Drive Committee, 353
- Production, illumination and, 354
 rate, manpower and, 383
 working hours and, 335
- Professional agencies, activities of, in industrial health, 123
 personnel, shortage of, 9
- Projectiles, renovation, dermatitis and, 191
- Protective industrial lighting, minimum illumination for, 367
 ointments, formulas, 170-172
- Protoscope manufacture, health hazards in, 249
- Protein, recommended daily allowance, 329
 requirements, 326
- Psychiatric bulk in industry, classification, 294
 percentage of total employees, 294, 295
 factors, in absenteeism, 456
- Psychiatry, industrial, 291-296
 as part of field of industrial medicine, 292
 justification and need for program, 291
 limits of field of, 293
 problems of, 63
- Psychic disturbance in mercury poisoning, 148
- Psychological factors, in absenteeism, 458
 in fatigue, 311, 313
- Psychoneurosis in industrial workers, 294
- Psychopathic personalities among industrial workers, 294
- Psychosis, in industrial workers, 294
 selective placement policy and, 391
- Public health agencies, services offered by, 38-40
- Public health education, sources of information to aid in, 41
- Public health program, place of industrial hygiene in, 122
- Public Health Service, standard milk ordinance of, 342
- Public works in war areas, 2
- Publicity in nutritional education, 331

- Puerto Rico, U.S.P.H.S. District including, 15
- Pulmonary fibrosis, occupational, 150. See also *Silicosis*.
- tuberculosis. See *Tuberculosis*.
- Purpura in benzene poisoning, 155
- QUACKERY and health education, 304
- Quarterly frequencies in sickness absenteeism, 432, 433, 434
- RACE as factor in sickness absenteeism, 435
- Radiant energy, hazards from, 369-371
- Radioactive dust in luminous dial painting, 237
- materials, exposure to, 369
- Radium, and physical examination, frequency of, 51.
- damage by, types of rays in relation to, 149
- dental services and, 90
- exposure to, 369
- harmful effects, causes of, 149
- industrial uses of, 148
- poisoning, 148-150
- bone lesions in, 149, 150
- chronic nature of, 149
- jaw necrosis in, 149
- medical control, 150
- symptoms, 149
- treatment, 150
- decalcification therapy, 150
- protection chart, Failla, 370
- radiant energy from, 370
- Radon, 149
- in luminous dial painting, 237
- sources, 238
- test, expired air, 150
- Range, casualty, health hazards of, 220
- function, health hazards of, 220
- hangfire, health hazards of, 220
- penetration, health hazards of, 220
- velocity, health hazards of, 220
- Rat, community sanitation and, 343
- Rayon manufacturing, minimum illumination for, 365
- Receiving, minimum illumination for, 363
- Records, absenteeism, 459, 460, 461
- Recreation, in combating fatigue, 322
- time, production and, 335
- women in industry and, 415
- Red Cross, nutritional education and, 383
- Refuse disposal, community sanitation and, 342
- Rehabilitation, clinics for, 5
- medical, 389
- physical, 389
- recommendations, 392
- surgical, 389
- war production and, 384
- Reporting of occupational diseases, 119, 129
- of venereal diseases by industrial physician, 289
- Research Section, Division of Industrial Hygiene, National Institute of Health, 110
- Research, war, Division of Industrial Hygiene in, 125
- Resorcinol aerosol, 271
- Resorcinol-glycerine aerosol, 271
- Resources available in field of industrial medicine, 106-130
- Respiration, artificial, in carbon monoxide poisoning, 156
- Respirators, abrasive blasting, 209
- air-line, 209
- for cold tinning process, 224
- in degreasing, 227
- in mercury crack testing, 240
- air-purifying, 207, 208
- approval of, by U. S. Bureau of Mines, 210
- chemical-cartridge, 208
- in amatol preparation, 217
- chemical-filter, 208
- in magnesium casting, 239
- in mercury crack testing, 240
- in protectoscope manufacture, 249
- classification table, 208
- dust, 208
- filter, in amatol breakup, 216
- in booster cup loading, 222
- fume, 208
- maintenance of, 211
- mechanical-filter, 208, 226
- for pneumoconiosis dusts, 231
- in DNT crushing and screening, 228
- in igniter mixture preparation, 234
- in primer mixture screening, 248
- in soldering, 252
- in sweetie barrel operation, 253
- in tetryl blending, 253

- Respirators, mechanical-filter, in
 - TNT cooling, 257
 - in TNT screening, 260
 - in tracer mixture blending, 261
- mist, 209
- selection of, 210
- supplied-air, 207, 209
 - in brush painting, 245
 - in furnace lining removal, 231
 - in lead burning, 235
 - in luminous dial painting, 238
 - in rubber goods fabrication, 250
 - in soldering, 252
 - in spray painting, 246
 - in sweetie barrel operation, 253
- toxic-dust, in grinding, 233
- Respiratory disease, air conditioning
 - and, 380
 - as cause of absenteeism, 427, 428, 433, 437, 438, 440, 444, 445, 447, 453, 454
 - in food handlers, examination for, 54
 - medical control of, 267-277
 - conclusions regarding, 276
 - problems presented by industry, 267
 - selective placement policy and, 391
 - streptococcic sore throat, in food handlers, 54
- Respiratory infections, acute, 267
 - air-borne hypothesis, 270
 - environmental control, 270
 - aerosols, 271
 - sunlight, 270
 - ultraviolet radiation, 270
 - general control measures, 271
 - hygiene and sanitation during epidemics, 271
 - immunization measures, 269, 270
 - plant medical department and, 272
 - predisposing factors, 272
 - preemployment examination and, 272
 - chronic, 272
 - control programs, 273
- Respiratory symptoms, in cadmium poisoning, 146
 - in metal fume fever, 145
- Rest days, one per week essential, 317
- Rest pauses, 320
 - for women workers, 404
- Rest pauses, value of, 317
- Rest rooms in plant infirmary, 20
- Restaurants, community sanitation
 - and, 342
 - facilities, nutrition and, 331
 - plant, manpower and, 399
- Rheumatic diseases as cause of absenteeism, 427, 428, 448, 448
- Rhode Island, U.S.P.H.S. District including, 14
- Riboflavin, recommended daily allowance, 329
- Rickets, 329
- Rodent control, community sanitation and, 343
- Roentgen ray, exposure to, 369
- Rosin melting, health hazards in, 249
- Rubber, as dermatitis preventive, 168
 - boat manufacture, health hazards in, 249
 - goods fabrication, health hazards in, 249
 - tire manufacturing, minimum illumination for, 363
- Rust preventives, dermatitis from, 181
- SAFETY department, relationship of medical department to, 36
- Safety education, compulsory participation not advisable, 300
 - coordination in one program and under one leadership, 299
 - duties of nurse in, recommendations on, 79
 - integration with community program, 300
 - medical supervision of, 299
 - training classes in, 301
 - workers' committees for, 300
- Safety, illumination and, 356
- Safety meetings, 212
- Salivation, excessive, in mercury poisoning, 148
- Salt, dermatitis caused by, 163
 - iodized, in dietary, 328
- Salvaging the handicapped, 4, 5, 384, 389, 392
- Sand, in ballistics testing, 220
 - mixing, health hazards in, 250
 - screening, health hazards in, 250
 - shot abrasive, health hazards with, 213
- Sandblasting, health hazards in, 213

- Sandblasting, housekeeping in, 214
 Sanitary engineer, industry and, 339
 Sanitation, community, 335-344
 definition, 335
 food sanitation and, 342
 garbage disposal and, 342
 housing and, 339, 340
 industry's effect on, 338
 milk control and, 341
 program for, 339
 refuse disposal and, 342
 sewage disposal and, 342
 water supply and, 340
 duties of nurse in, recommendations on, 79
 inspection in, role of nurse in, 71
 plant, 345-352
 atmospheric sanitation and, 345
 womanpower and, 399
 role of nurse in, recommendations on, 79
 Saranac Laboratory for the Study of Tuberculosis, interest in industrial hygiene, 123
 Schedule compensation laws versus general coverage laws, 135
 Scurvy, 329
 Sea food in dietary, 328
 Season, epidemics and, effect on sickness absenteeism rates, 429, 430, 431
 Second-injury provisions in compensation laws, 138
 States with, 138
 Selective placement, policy for, 390
 Selenium, water pollution from, 338
 Self-diagnosis and health education, 304
 Self-sealing fuel tank manufacture, health hazards in, 249
 Self-treatment and health education, 304
 Sensitizers, cutting oils as, 176
 dermatitis and, 162
 Serology, positive, rejection rate due to, 384
 Services, available, in industrial hygiene, 106-130
 Seven-day waiting period, effect on sickness absenteeism rates, 452
 Severity rate in sickness absenteeism, 421
 Sewage disposal, community sanitation and, 342
 plant sanitation and, 347
 Sex differences in sickness absenteeism, 425, 427, 435, 436, 437, 438, 439, 440
 Shadows, accidents and, 356
 Sheet metal works, minimum illumination for, 364
 Shell case manufacture, health hazards in, 251
 loading, dermatitis and, 191
 plants, minimum illumination for, 367
 Shellfish industries, community sanitation and, 342
 Shift rotations, fatigue and, 318, 321
 schedules, womanpower and, 403
 Shifts, work, and fatigue, 8
 Shipping, minimum illumination for, 363
 Shipyards, minimum illumination for, 367
 Shoes, comfortable, on job, 320
 for women in industry, 411
 manufacturing, minimum illumination for, 364
 Shotblasting, health hazards in, 214
 Showers, plant sanitation and, 347
 Shrapnel projectile loading, health hazards of, 249
 Sick benefit organizations, factors affecting absenteeism rates, 422, 423, 453
 Sickness absenteeism, 420
 among women, 412
 control of, 462
 days of disability contributed by disabilities of seven days or less, 439, 440
 disability rate, 421
 by broad cause and age groups from absences contributing t days or less, 446, 447
 by broad cause groups for absences lasting one calendar day or more, 452, 453, 454
 duration of disability, 435
 frequency and duration of, 441, 441, 442
 frequency rate, 421
 by broad cause and age groups for absences lasting t days or more, 443, 444
 by broad cause groups from absences lasting one calendar day or more, 449, 451
 in women and men, 412
 malingering and, 423

- Sickness absenteeism, miscellaneous factors in, 456
 nonrespiratory causes and age, 448
 nonrespiratory - nondigestive causes and age, 448, 448
 per cent of workers compensated, 456, 457
 percentage distribution, according to broad cause groups, of days disabled on specific days of disability after onset, 437, 438
 rates, 421
 causes of differences, 422
 comparability of, 422
 effects of age, 423, 425, 428, 429, 443, 444, 446, 447, 448, 448, 456, 457
 of epidemics and season, 429, 430, 431
 of maximum benefit period, 422, 424, 455
 of notification, certification, and verification procedures, 423
 of occupation, 434
 of racial differences, 435
 of season, 429
 of sex, 425, 427, 435, 436, 437, 438, 439 440
 of time-changes, 430, 443
 quarterly frequencies, 432, 433, 435
 of waiting period, 422, 423, 452
 factors yielded by sick benefit organizations, 422, 423
 frequency of factors affecting, 423
 types of, 421
 severity rate, 421
- Sickness, disabling, causes of, 427, 428, 433, 437, 438, 440, 443, 444, 446, 447, 448, 448, 449, 451, 452, 453, 454
 duration of, 435
 frequency and distribution of, 424, 425, 426, 427
 and duration of, 441, 441, 442
 related to various factors and indexes, 424
 physical examination following, 52
 Siderosilicosis, 151
 Siderosis, 151
 Silica dust, in ballistics testing, 219
 Silica dust, in furnace lining removal, 231
 in sand mixing and screening, 250
 Silica, free, in sandblasting, 218
 in shotblasting, 214
 Silica sand as health hazard, 7
 Silica, toxic limit of, 264
 Siliceous dusty trades, frequency of periodic X-ray in, 275
 Silicosis, 150
 accrued liability in, 137
 classification, 151
 control programs, 273
 definition, 150
 diagnosis, 153
 etiology, 151
 exposures necessary for development, 152
 history in, 152, 153
 incidence, 152
 limiting provisions in compensation laws, 137
 medical control measures, 154
 periodic medical examinations to prevent, 154
 States providing coverages for, 152
 symptoms and signs, 152
 tuberculosis and, 154
 working conditions necessary for production of, 152
 X-ray findings, 153
 Silk manufacturing, minimum illumination for, 365
 Skin, and varicosities, rejection rate due to, 384
 cleaners, dermatitis, 173
 formula, 173
 cracking, cutting oils and, 177
 cutting oils and, 176
 diseases, selective placement policy and, 196, 391
 drying, cutting oils and, 177
 fissuring, cutting oils and, 177
 irritants, protective ointment against, 172
 shower specifications and, 347
 occupational hazards, 139
 protection in welding, 182
 Slaughter houses, community sanitation and, 342
 Sleep, adequate, and fatigue, 322
 Sleeves, dermatitis prevention and, 169
 Smoke pollution, community sanitation and, 337

- Smokeless powder, 242
- Soap, dermatitis and, 173
 manufacturing, minimum illumination for, 364
 plant sanitation and, 347
 substitutes, 174
- Social causes of illness, need for knowledge of, 106
 factors in absenteeism, 458
- Social Hygiene Association, 41
- Sodium chloride in dietary, 327, 328
- Soldering, health hazards of, 252
- Solvents, dermatitis from, 175, 193
 new, as health hazards, 7
- Sore throat, septic, community sanitation and, 341
- South Carolina, U.S.P.H.S. District including, 14
- South Dakota, U.S.P.H.S. District including, 15
- Speed-up in industry as health hazard, 6, 320
- Spray coating, health hazards in, 245
- Sprays, chemical, in control of acute respiratory infections, 271
- Sputum, asbestosis bodies in, 154
 blood-tinged, in silicosis, 153
- Stairways, minimum illumination for, 364
- State governments, joint interdepartmental action in industrial hygiene field, 118
- State health departments, functions:
 control of venereal diseases, 283, 285
 establishment of industrial hygiene, 108, 109
 organization and practice of industrial hygiene services, 111
 public health education, 41
- State health departments, relationship of plant medical department to, 38
- State industrial hygiene division, 111
 integration of health services by, 114
 types of services possible, 112
 war assistance by Division of Industrial Hygiene, 125
- State industrial hygiene divisions, functions:
 chemical, 113
- State industrial hygiene divisions, functions:
 engineering, 113
 medical, 112
 nursing, 113
- State Vocational Rehabilitation Services, 389
- States, Districts Nos. 1-9 of U.S.P.H.S., 14-15
 legislation of, on employment during pregnancy, 407
 on weight lifting by women, 408
 occupational diseases compensable, list of, 133
 occupations forbidden to women in, 402
 types of compensation laws in, 135
 venereal disease control program, 283
 with compensation coverage of agricultural and domestic workers, 137
 with provisions for silicosis, 152
 with second-injury provisions, 138
- States Relations Section, Division of Industrial Hygiene, National Institute of Health, 110
- Statistical Unit, Division of Industrial Hygiene, National Institute of Health, 110
- Steam out, health hazards of, 216
- Steel manufacturing, minimum illumination for, 362
- Steel shot abrasive, health hazards with, 213
- Stereoroentgenography in tuberculosis control, 274
- Stippling of erythrocytes in lead poisoning, 143
- Stoddard solvent dermatitis, 193
- Stomatitis, in mercury poisoning, 148
 vitamin deficiency and, 329
- Stone crushing, minimum illumination for, 364
 screening, minimum illumination for, 364
- Storage battery manufacturing, minimum illumination for, 364
- Storage space in plant infirmary, 23
- Storerooms, minimum illumination for, 364
 minimum window requirement for, 376

- Stores, community sanitation and, 342
- Strength, physical, womanpower and, 407
- Stretcher teams, organization of, in emergency medical services, 102
- Structural steel fabrication, minimum illumination for, 364
- Subnutritive state, 325
- Substations of plant infirmary, 17, 21, 23
- Sugar, dermatitis caused by, 163
grading, minimum illumination for, 364
- Sulfation, dimethylaniline, health hazards in, 228
- Sulfur, dermatitis and, 176
requirements, dietary, 327
- Sulfur dioxide, as skin irritant, 176
in leather cleaning, 236
in magnesium casting, 239
in pickling, 247
toxic limit of, 264
- Sulfuric acid gas, health hazard of, 216
- Sunlight in control of acute respiratory infections, 270
- Surgical rehabilitation, 389
- Surveys, community hospital and health facilities, 14
plant, participation in, by plant physicians, 129
preliminary, to determine problems of industrial hygiene, 109
- Sweeping, plant sanitation and, 351
- Sweetie barrel operation, health hazards of, 252
- Syphilis, 278. See also *Venereal diseases*.
blood tests, injustices from, 281, 282
costs, to industry and society, 280
disability due to, 280
employment policy in, 282, 284, 287, 288
in preplacement examination, 57
prevalence of, 279
regional distribution, 279
rejection rate due to, 384
selective placement policy and, 390, 391
- Syphilitic aortitis, employment considerations and, 60
- TANK manufacture, health hazards of, 249
minimum illumination for, 367
- Tar compounds, dermatitis caused by, 163
- Teamwork, need for, in wartime industrial medicine, 9
- Technicians, activities of, recommendations on, 81
laboratory, 34
role in physical examination, 47
X-ray, 34
- Teeth, defective, rejection rate due to, 384
selective placement policy and, 390
- Temperature, plant, factors determining, 373
- Tennessee, U.S.P.H.S. District including, 14
- Testing, ballistics, health hazards of, 219
minimum illumination for, 364
- Tests of fatigue, 312
- Tetrachloroethane, toxic limit of, 264
- Tetrachloroethylene, toxic limit of, 264
- Tetryl, 45
and physical examination, frequency of, 51
blending, health hazards of, 253
crystallization, health hazards of, 253
dermatitis, 191
diagnosis, 182
prevention, 183, 192
symptoms, 182
treatment, 184
drying, health hazards of, 254
dust, in booster cup loading, 222
manufacture, dermatitis in, 184
mixing with TNT, health hazards of, 254
packing, health hazards of, 255
pellet density testing, health hazards of, 247, 255
pelleting, health hazards of, 255
reaming, health hazards of, 255
screening, health hazards of, 255
toxic limit of, 264
- Texas, U.S.P.H.S. District including, 15
- Textile industry, air conditioning in, 379
health hazards of, 379
- Textile mills, minimum illumination for, 364

INDEX

503

- Thiamin, recommended daily allowance, 329
- Thorium, exposure to, 369
- Ticks, community sanitation and, 343
- Time changes, effects of, on sickness absenteeism rates, 430, 443
quarterly frequencies, 432, 433, 434
factor in occupational diseases, importance of, 140
lost from job, as measure of health, 421
- Tinning process, cold, health hazards in, 224
- Titanium, water pollution from, 338
- TNT, 45
and physical examination, frequency of, 51
break-up, health hazards of, 216
cooling, health hazards of, 256
dermatitis, 162, 192
prevention, 192
drying, health hazards in, 257
dust, dermatitis from, 185
in booster cavity drilling, 222
flaking, health hazards in, 257
fumes, in amatol bucket cleaning, 216
in amatol cooling, 217
in amatol pouring, 217
in amatol preparation, 217
graining, health hazards in, 258
in amatol dust, health hazard of, 216
in primer mixture screening, 248
in toluene nitration, 260
manufacture, dermatitis from, 185
melting, health hazards in, 258
metal tub cleaning, health hazards in, 258
pouring and puddling, health hazards in, 217
purification, health hazards in, 259
screening, health hazards in, 259
tetryl mixing with, health hazards of, 254
toxic limit of, 264
- Tobacco products, minimum illumination for, 365
- Toilet facilities, community sanitation and, 342
plant sanitation and, 347
specifications, 347
- Toilet rooms, location of, 348
- Toilet rooms, minimum illumination for, 365
minimum window requirement for, 376
of plant infirmary, 22
- Toluene, and physical examination, frequency of, 51
nitration, health hazards in, 260
toxic limit of, 264
- Toluol, in rubber goods fabrication, 249
toxic limit of, 264
- Tool and die shop, dermatitis in, 191
- Towels, plant sanitation and, 347
- Toxic limits, table of, 264
metals or metalloids, diseases caused by, 139
substances, new, use in industry, 7
- Tracer bullet charging, health hazards in, 260
mixture blending, health hazards in, 261
screening and mixing, health hazards of, 261
- Training of employees in job, 320
of worker in health matters, 301
- Transportation, of worker, and fatigue, 317, 321
women in industry and, 415
- Treatment, emergency, opportunities for health education at, 297
rooms of plant infirmary, 19
- Tremors in mercury poisoning, 148
- Trench mortar shell loading, dermatitis and, 191
- Trichinosis, garbage disposal and, 342
- Trichlorethylene, in type cleaning, 248
toxic limit of, 264
vapors, in degreasing, 226
- Trinitrophenylmethylnitramine. See *Tetryl*.
- Trinitrotoluene. See *TNT*.
- Troops, migration of, community sanitation and, 343
- Truck drivers, fatigue in, study of, 311
- Tuberculosis, 273
arrested, employability of worker with, 276
control programs, 273
administrative procedures, 274
effectiveness of, 273
frequency of periodic X-ray, 275

- Tuberculosis, control programs,
X-ray methods in, 274
employment considerations and,
59
follow-up, after-care, rehabilita-
tion, 275
in preplacement examination, 57
milk-borne, and community sani-
tation, 341
prevalence in industry, 272
in plants, X-ray surveys, 273
primary, healed, employability of
applicant with, 275
pulmonary, silicosis and, 154
reinfection, inactive, employability
of applicant with, 275
reporting to health authorities,
38, 39
selective placement policy and, 390
X-ray examination for, 59
Turpentine, toxic limit of, 264
Type cleaning, health hazards in,
248
Typhoid fever, community sanita-
tion and, 341, 343
examination for, in food han-
dlers, 54
in preplacement examination, 57
Typhus, community sanitation and,
343
- ULTRAVIOLET radiation, from mer-
cury vapor lamps, 369, 371
from welding arc, 262, 369
of air in control of acute respir-
atory infections, 270
- Undulant fever, community sanita-
tion and, 341
- Unit heaters, 375
- United Service Organizations, med-
ical director and, 41
- Upholstering, minimum illumina-
tion for, 365
- Urinals, specifications, 348
- Urine, in benzene poisoning, 155
lead content, normal and ab-
normal, 143, 144
- U. S. Bureau of Mines, 108
joint action with U. S. Public
Health Service in industrial
hygiene field, 117
respirator approval by, 210
- U. S. Civil Service Commission,
handicapped worker and, 388
- U. S. Department of Agriculture,
nutritional education and, 333
- U. S. Department of Interior, Fish
and Wildlife Service, 40
- U. S. Department of Labor, joint
action with U. S. Public Health
Service in industrial hygiene
field, 117
services offered by, 40
statement on pregnancy, 405
work of, in field of industrial
medicine, 108
- U. S. Department of Labor, Chil-
dren's Bureau, 40, 108
care of children of working
mothers, 417
statement on pregnancy, 405
- U. S. Department of Labor, Divi-
sion of Labor Standards, 40, 108
- U. S. Department of Labor, Women's
Bureau, 40, 108, 395, 400
classes of industrial areas, 416
clothing standards, 410, 411
employment of women, 4
current information on, 402
lunch period, 400
night work, 402
types of work, 396
under war conditions, recom-
mendations, 400
weight lifting, 408, 409
statement on pregnancy, 405
- U. S. Employment Service, job
analysis and, 387
- U. S. Office of Civilian Defense,
Medical Division, protection of
medical plants, requirements for,
98
- U. S. Public Health Service, estab-
lishment of industrial hygiene
work in State and local depart-
ments of health, 108
industrial dental consultative serv-
ice, dental services and, 91
joint action with other Federal
agencies, 117
- National Institute of Health. See
National Institute of Health.
photofluorographic units, 274
present organization and practice
of industrial hygiene in, 109
professional personnel shortage
and, 9, 10
recommendations for control of
venereal diseases in industry,
282
relationship of plant medical de-
partment to, 39

- U. S. Public Health Service, services offered by, 39
- standard milk ordinance of, 342
- training of professional workers, 2
- U. S. Public Health Service Districts, 14
- Nos. 1-9, 14-15
- Offices, services offered by, 39
- U. S. Public Health Service, Division of Sanitary Reports and Statistics, public health education, 41
- U. S. Public Housing Authority, services available from, 40
- Utah, U.S.P.H.S. District including, 15
- VACATIONS, 404
 - in overcoming fatigue, 317, 320
- Vaccines in prevention of colds, 269
- in prevention of influenza, 270
- Valvular disease. See *Heart disease*.
- Vapors, definition, 198
- diseases caused by, 139
- Varicocele, rejection rate due to, 384
- selective placement policy and, 390, 391
- Varicosities, selective placement policy and, 390, 391
- Varsol in leather cleaning, 236
- Vascular disease as cause of absenteeism, 448, 449
- Venereal diseases, absenteeism due to, 281
 - blood tests, injustices from, 281, 282
 - conclusions regarding, 289
 - control of, 278-290
 - administration of program, 285
 - agency cooperation, 283
 - conference with industrial physician, 288
 - correlation of industrial and community programs, 284
 - developing a program, 283
 - educational program, 285
 - employment examinations, 287
 - follow-up of infected workers, 289
 - in industrial workers, 279
 - in small plants as well as large, 281
 - industry's stake, 280
 - justification and need for a program, 280, 281
 - Venereal diseases, control of, morbidity reporting, 289
 - new public interest in, 278
 - objectives of program, 282
 - from standpoint of employee, 283
 - of industry, 282
 - plant committee, 283
 - recommendations of U. S. Public Health Service, 282
 - State health departments in, 283, 285
 - costs, to industry, 280
 - to society, 280
 - employment of infected persons, 282, 284, 287, 288
 - examination results confidential, 281, 286
 - in food handlers, overemphasis upon, 53
 - physical examination and, 49
 - plant policy and, 49
 - prevalence of, 278
 - reporting to health authorities, 38, 39, 289
 - status of employees with, 287
- Ventilation, 376-378
 - dilution, 206
 - exhaust, 199
 - general, 206
 - mechanical, 377
 - body odor and, 377
 - in blacked-out building, 377
 - in cooling season, 377. See also *Air conditioning*.
 - natural, 376
 - window requirement for, 376
 - rate, factors determining, 376
- Verification, method of, as factor in sickness absenteeism rates, 423
- Vermont, U.S.P.H.S. District including, 14
- Veterans Administration, hospitalization by, 40
- Vinylite as dermatitis preventive, 168
- Virgin Islands, U.S.P.H.S. District including, 15
- Virginia, U.S.P.H.S. District including, 14
- Vision, adequacy of, 62
 - binocular, test for, 62
 - correction of, facilities for, 62
 - defective, increase of, 61
 - rejection rate due to, 384
 - selective placement policy and, 390, 391

- Vision, defective, types of, 61
illumination and, 62
standards for, 61
tests of, 62
for special tasks, 62
vitamin deficiency and, 329
Visiting nurse, community nurse as, 73
family nursing and, 73
in small plant organization, 58
industrial nurse as, 72
service, aims of, 73
Visual acuity, relation of illumination to, 355
Vitamin A, 329
Vitamin B₁, 329
Vitamin B₂, 329
Vitamin C, 329
Vitamin D, 329
Vitamin G, 329
Vitamin requirements, dietary, 328
Vocational rehabilitation, 389
Vocational Rehabilitation Services, 389
- WAITING period, any chosen length, effect on annual number of days of disability, 455
effect on sickness absenteeism rates, 422, 423
seven-day, effect on sickness absenteeism rates, 452
under compensation laws, 136
Waiting rooms of plant infirmary, 18
Waiver clauses in compensation laws, 138
War areas, health and other facilities, 2
War conditions, effect on mental health of workers, 291, 292, 294
fatigue and, 308
War effort, cooperation of medical profession in, 126
industrial hygiene in, 124, 127
War housing, 2, 3
War industries, community environment and, 1
composition of labor force, 3
fatigue as problem in, 7
handicapped workers, utilization of, 4, 5
manpower need, 3
occupational diseases and, 139
shortage of physicians in, 9
War industries, shortage of trained personnel in, 9
uneven geographical allocation, 1
women in, 4
working environment, 6
War, influence of, on industrial hygiene, 1-11
War Manpower Commission, estimates on manpower, 3
Procurement and Assignment Division, 9
salvaging the handicapped, 5
War plant, appraisal of community hospital and health facilities before building, 14
inspection of, 125
medical facilities of, 12-24
War Production Board, cooperation of Division of Industrial Hygiene with, 126
women in industry and, 4
War production, illumination requirement table, 367
War research, Division of Industrial Hygiene in, 125
War workers, dislocated, and immunization, 55
Warehouse, minimum illumination for, 365
Wartime problems, community environment, 1
composition of war labor force, 3
demands on industrial physician, 8
shortage of professional personnel, 9
working environment, 6
Washing facilities, plant sanitation and, 347
Washington, U.S.P.H.S. District including, 14
Washrooms, minimum illumination for, 365
specifications for, 347
Waste, disposal of, specifications for, 346
industrial, water pollution and, 338
Watch manufacturing, minimum illumination for, 362
Water, contaminant control by, 205
drinking, community sanitation and, 337
pollution, 338
supply, community sanitation and, 340

- Water supply, plant sanitation and, 345
- Water-borne epidemics, reporting to health authorities, 39
- Weakness, meal frequency and, 326
- Weight lifting, womanpower and, 408
 - loss, vitamin deficiency and, 329
- Welding, dermatitis from, 182
 - electric, as health hazard, 6
 - health hazards of, 262
 - minimum illumination for, 361, 365
 - operations, protection for, 369
 - tabulation, 370
 - radiation, hazards in, 262, 369
- Welfare department, relationship of medical department to, 37
- Welfare policies in combating fatigue, 321
- Welfare program, duties of nurse in, recommendations on, 79
 - family social problems, 72, 79
 - financial aid, 72
 - hospital insurance, group basis, 72, 79
 - recreation, 72, 79
 - role of nurse in, 72
 - recommendations on, 79
 - sick benefits, group basis, 72, 79
- West Virginia, U.S.P.H.S. District including, 14
- Western Electric Company, rehabilitation in, 389
- Westinghouse Electric and Manufacturing Company, rehabilitation in, 389
- Whitfield's ointment, for athlete's foot, 195
- Window requirements, for natural ventilation, 376
- Wisconsin, joint interdepartmental action in industrial hygiene field, 118
 - U.S.P.H.S. District including, 14
- Womanpower, 383, 395. See also *Manpower*.
- Women in industry, 395-419
 - absenteeism, 412
 - industrial injuries, 413
 - nonindustrial injuries, 413
 - occupational diseases, 413
 - personal reasons, 414
 - sickness, 412
 - cafeterias, 399
- Women in industry, care of children, 416
 - changes in plant facilities necessitated by, 398
 - clothing, 409
 - community relationships, 414
 - employment of, 3, 395
 - forbidden occupations, 401
 - hours of work, 402
 - housing, 415
 - job analysis, 398
 - leaves of absence, 404
 - legal restriction on working hours, 400
 - lunch periods, 404
 - married, employment of, 397
 - menstrual periods, 407
 - order of employment, 397
 - physical examination, 47, 48
 - physical strength, 407
 - pregnancy, 405
 - recreation, 415
 - rest periods, 404
 - seating, 399
 - selection, 397
 - shift schedules, 403
 - sources of female labor, 396
 - toilet and rest room facilities, 350, 399
 - training, 397
 - transportation, 415
 - weight lifting, 408
- Women's Bureau, U. S. Department of Labor, 40, 108, 396, 400, 402
 - employment of women, 4
 - statement on pregnancy, 405
- Women's Field Army Against Cancer, 41
- Wood veneer processing, health hazards of, 263
- Woodworking, minimum illumination for, 365
- Woolen mills, minimum illumination for, 365
- Work, disinclination to, in hunger, 326
 - hours, optimum, for sustained production, 315
 - schedules, full day of rest per week, importance of, 317
 - shifts, fatigue and, 8
 - rotations, fatigue and, 318
 - situation, general, and absenteeism, 458

- Work weeks, optimum, length of, 315, 316, 317, 320
 Worker, education of, in housekeeping, 212
 handicapped. See *Handicapped workers*.
 health of, sanitation and, 335
 migrations of, community sanitation and, 343
 night shift and, 402
 responsibilities of, in air contaminant control maintenance, 211
 in plant housekeeping, 212
 selection of, dermatitis and, 196
 Working environment, as factor in fatigue, 319
 problems of, 8
 womanpower and, 400
 Workmanship, illumination and, 354
 Workmen's compensation. See *Compensation*.
 Workroom, minimum window requirement for, 376
 Wrist drop, in lead poisoning, 142
 Wyoming, U.S.P.H.S. District including, 15

 X-RAY diagnosis of asbestosis, 154
 of silicosis, 153

 X-ray examination of chest, administrative procedures, 274
 frequency of, in siliceous dusty trades, 275
 in workers with evidence of tuberculosis, 275
 in control of chronic respiratory infections, 273
 methods, 274
 X-ray facilities of plant infirmary, 22
 miniature films in chest surveys, 274
 technicians, 34
 testing equipment, radiant energy from, 369
 Xylene, in lens cleaning, 236
 toxic limit of, 264
 Xylol, in rubber goods fabrication, 249
 toxic limit of, 264

 ZINC chloride, dermatitis from, prevention, 195
 Zinc oxide fever, 145
 fumes, in shell case manufacture, 251
 in welding, 262
 toxic limit of, 264
 Zinc sulfide in luminous dial painting, 237